# Symantec NetBackup Clustered Master Server Administrator's Guide

for Windows, UNIX, and Linux

Release 7.5



#### Symantec NetBackup Clustered Master Server Administrator's Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Documentation version: 7.5

#### Legal Notice

Copyright © 2012 Symantec Corporation. All rights reserved.

Symantec and the Symantec Logo are trademarks or registered trademarks of Symantec Corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

This Symantec product may contain third party software for which Symantec is required to provide attribution to the third party ("Third Party Programs"). Some of the Third Party Programs are available under open source or free software licenses. The License Agreement accompanying the Software does not alter any rights or obligations you may have under those open source or free software licenses. Please see the Third Party Legal Notice Appendix to this Documentation or TPIP ReadMe File accompanying this Symantec product for more information on the Third Party Programs.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation 350 Ellis Street Mountain View, CA 94043

http://www.symantec.com

#### **Technical Support**

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

#### **Contacting Technical Support**

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
  - Error messages and log files
  - Troubleshooting that was performed before contacting Symantec
  - Recent software configuration changes and network changes

#### Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

#### Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs, DVDs, or manuals

#### Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare\_apac@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America supportsolutions@symantec.com

# Contents

Technical Su	pport	4
Chapter 1	Introduction to NetBackup Master Server Clustering	11
	About this guide  About NetBackup clustering  About NetBackup failover server data protection in a cluster  About NetBackup failover server support  NetBackup supported cluster solutions  Accessing NetBackup cluster compatibility lists  About configuring LiveUpdate with clustered NetBackup	11 12 12 13
	About NetBackup limitations with clustering solutions	
Chapter 2	NetBackup in a Microsoft Cluster Server	17
	About NetBackup on Microsoft Cluster Server Installation prerequisites for NetBackup on MSCS cluster Installing a NetBackup failover server on MSCS cluster Configuring a NetBackup server on MSCS cluster Upgrading a NetBackup failover server on MSCS cluster Restoring the cluster quorum Restoring the cluster quorum to a node with directory services Preparation for disaster recovery of MSCS Disaster recovery of MSCS Recovering the entire MSCS cluster Recovering all shared disks About recovering NetBackup data on a shared disk	18 19 20 21 25 25 26 26
Chapter 3	NetBackup in a Veritas Cluster Server on UNIX/Linux	29
	About NetBackup on a Veritas Cluster Server on UNIX/Linux Installation prerequisites for NetBackup on VCS on UNIX/Linux About preinstallation checklist for a NetBackup failover server	
	installation on VCS on Unix\Linux	31

	NetBackup installation information for all VCS	
	configurations	31
	NetBackup installation information for specific VCS	
	configurations	32
	Installing a failover NetBackup server on VCS on UNIX/Linux	33
	Configuring a failover NetBackup server on VCS on UNIX/Linux	35
	About adding a node to existing cluster	36
	Installing or upgrading NetBackup database agents and options on	
	VCS on UNIX/Linux	36
	Upgrading a NetBackup failover server on VCS on Unix/Linux	37
Chapter 4	NetBackup in a Veritas Cluster Server on Windows	
		41
	About NetBackup in a Veritas Cluster Server on Windows	41
	About NetBackup agent for VCS on Windows	42
	Installation prerequisites for NetBackup on VCS on Windows	42
	Installing a NetBackup failover server on VCS on Windows	
	Configuring a NetBackup server on VCS on Windows	45
	Upgrading a NetBackup failover server on VCS on Windows	
	About detailed monitoring for the NetBackup server	
	Setting up a detailed monitoring script for the NetBackup server on	
	VCS on Windows	47
	Enabling detailed monitoring in VCS Cluster Manager for the	
	NetBackup server	48
	Disabling detailed monitoring in VCS Cluster Manager for the	
	NetBackup server	49
Chapter 5	NetBackup in a SunCluster	<b>51</b>
Chapter 5	Netbackup III a Suliciustei	51
	About NetBackup on SunCluster	51
	Installation prerequisites for NetBackup on SunCluster	52
	Preinstallation checklist for a NetBackup failover server installation	
	on SunCluster	53
	Installing NetBackup on SunCluster	53
	Configuring NetBackup on SunCluster	55
	Installing or upgrading NetBackup database agents and options on	
	SunCluster	56
	Upgrading a NetBackup failover server on SunCluster	57
	SunCluster commands for bringing the resource group online or	
	offline	58

Chapter 6	NetBackup on HP Service Guard cluster	61
	About NetBackup on HP Service Guard cluster	61
	cluster Preinstallation checklist for a NetBackup failover server installation	
	on HP Service Guard cluster	
	Installing NetBackup on HP Service Guard cluster	
	Configuring NetBackup on HP Service Guard cluster	66
	Installing or upgrading NetBackup database agents and options on	
	HP Service Guard Cluster	67
	Upgrading a NetBackup failover server on HP Service Guard	60
	Cluster	68
	offline	70
	orinite	70
Chapter 7	NetBackup on HACMP cluster for AIX	71
	About NetBackup on HACMP cluster for AIX	71
	Installation prerequisites for NetBackup on HACMP cluster for AIX	
		72
	Preinstallation checklist for a NetBackup failover server installation	
	on HACMP cluster for AIX	
	Installing NetBackup on HACMP cluster for AIX	
	Configuring NetBackup on HACMP cluster for AIX	75
	Installing NetBackup database agents and options on HACMP cluster	
	for AIX	76
	Upgrading a NetBackup failover server on HACMP cluster for	70
	AIX	
	Bringing the NetBackup resource group online or offline	80
Chapter 8	Configuring NetBackup	81
	NetBackup configuration overview	82
	NetBackup configuration guidelines	
	Device configuration guidelines	84
	Configuring devices	85
	Configuring NetBackup catalog backups in a cluster	86
	About configuring backup policies for a NetBackup clustered	
	server	
	What to back up	
	Guidelines for backing up local disks in a cluster	
	Guidelines for backing up the shared disks	88
	Verifying NetBackup configuration	89

Configuring robotic daemons for monitoring (UNIX/Linux	
clusters)	89
Configuring additional services (UNIX/Linux clusters)	90
Configuring add-ons for monitoring (UNIX/Linux clusters)	91
Configuring additional services (Windows)	91
Configuring add-ons for monitoring (Windows)	92
About adding license keys	92
Operational notes	93
General notes on clustered master server administration	93
About NetBackup's IPv6 support	97
NetBackup master server in a cluster using multiple	
interfaces	99
About NetBackup master server in a cluster using multiple	
	99
Requirements for use of a NetBackup master server in a cluster with multiple interfaces	101
Configuring the NetBackup master server in a cluster using multiple interfaces	101
	clusters)  Configuring additional services (UNIX/Linux clusters)  Configuring add-ons for monitoring (UNIX/Linux clusters)  Configuring additional services (Windows)  Configuring add-ons for monitoring (Windows)  About adding license keys  Operational notes  General notes on clustered master server administration  About delay in detecting of loss of connection (MSCS and VCS on Windows)  About MSCS clusters  About NetBackup cluster application management  Logging information  About NetBackup's IPv6 support  NetBackup master server in a cluster using multiple interfaces  About NetBackup master server in a cluster using multiple interfaces  Requirements for use of a NetBackup master server in a cluster with multiple interfaces

Chapter 1

# Introduction to NetBackup Master Server Clustering

This chapter includes the following topics:

- About this guide
- About NetBackup clustering
- About NetBackup failover server data protection in a cluster
- About NetBackup failover server support
- NetBackup supported cluster solutions
- Accessing NetBackup cluster compatibility lists
- $\blacksquare \quad About \ configuring \ Live Update \ with \ clustered \ Net Backup$
- About NetBackup limitations with clustering solutions

# About this guide

The Symantec NetBackup Clustered Master Server Administrator's Guide provides information about making NetBackup highly available by clustering theNetBackup master servers. Use the Symantec NetBackup Clustered Master Server Administrator's Guide to configure a clustered master server.

# **About NetBackup clustering**

Clusters provide high availability of applications and data to users. In a cluster, two or more servers (called nodes) are linked in a network. These servers run the cluster software that allows each node access to the shared disks. If a node becomes

unavailable, cluster resources migrate to an available node (this process is called failover). The shared disks and the virtual server are kept available. During failover, users experience only a short interruption in service.

In this documentation, the various cluster solutions are abbreviated as follows:

- Microsoft Cluster Server as MSCS
- Veritas Volume Manager as Volume Manager
- Veritas Cluster Server as VCS
- HP MC/Service Guard as Service Guard
- IBM's High Availability Cluster Multiprocessing as HACMP

#### About NetBackup failover server data protection in a cluster

NetBackup protects the data in a cluster environment in several ways.

When NetBackup is installed as a failover server, a NetBackup server is installed on the cluster as a virtual server application. Then the server can fail over from one of the nodes to the other. The server is assigned a network name resource (the virtual server name), an IP address resource, and a disk resource. The NetBackup server fails over from one node to another if a failure occurs on the active node. This failover provides high availability of the NetBackup server itself.

For failover master servers, the virtual server name is used as the name of the master server. This virtual name is used for all media servers and clients that use this master server.

When a failover occurs, the backup jobs that were running are rescheduled with the normal NetBackup retry logic for a failed backup. The NetBackup services are started on another node and the backup processing resumes.

The NetBackup failover master servers and media servers operate in an active or a passive failover configuration. The active node and the passive (or failover node) must be the same version of the master server.

The use of stand-alone media servers and NetBackup clients in a cluster is also briefly described later in this document.

# About NetBackup failover server support

For the NetBackup 7.5 release, the master server supports upgrade of clustered media servers. However, if the master server is also a media server, then the

master server also supports configuration of clustered media servers. For more information about supported NetBackup versions for upgrade, refer to the Symantec NetBackup Installation Guide.

The upgrade procedure for master and media server is the same.

Follow the instructions in the following *Upgrading a NetBackup failover server* sections for each clustering technology in this guide:

- See "Upgrading a NetBackup failover server on MSCS cluster" on page 21.
- See "Upgrading a NetBackup failover server on VCS on Unix/Linux" on page 37.
- See "Upgrading a NetBackup failover server on VCS on Windows" on page 46.
- See "Upgrading a NetBackup failover server on SunCluster" on page 57.
- See "Upgrading a NetBackup failover server on HP Service Guard Cluster" on page 68.
- See "Upgrading a NetBackup failover server on HACMP cluster for AIX" on page 78.

#### NetBackup supported cluster solutions

NetBackup supports several cluster environments. More information is available on how to install and configure NetBackup in particular type of cluster.

Table 1-1 lists the topics that describe how to install and configure NetBackup in each supported cluster environment.

Table 1-1	Supported cluster solutions
I anie T-T	Supported Cluster Solutions

Cluster solution	See
Microsoft Cluster Server	See "About NetBackup on Microsoft Cluster Server " on page 17.
Veritas Cluster Server Windows 2003, 2008, 2008R2	See "About NetBackup in a Veritas Cluster Server on Windows" on page 41.
Veritas Cluster Server on UNIX/Linux	See "About NetBackup on a Veritas Cluster Server on UNIX/Linux" on page 29.
SunCluster	See "About NetBackup on SunCluster" on page 51.
HP MC/Service Guard	See "About NetBackup on HP Service Guard cluster" on page 61.
HACMP for AIX	See "About NetBackup on HACMP cluster for AIX" on page 71.

# Accessing NetBackup cluster compatibility lists

The Symantec Support Web site now contains the most current platform support information for NetBackup. To locate the latest information on the Web site, perform the following procedure.

#### To access NetBackup cluster compatibility lists

- Go to the following Web site:
  - http://entsupport.symantec.com
- In the Find Your Product box, type NetBackup Enterprise Server and click the > option.
  - For Microsoft Cluster Server and Veritas Cluster Server for Windows, you also can indicate NetBackup Server.
- From the list on the right, click **Compatibility List**.
- For information on supported cluster environments, see the following list: Symantec NetBackup (tm) Enterprise Server x.x / NetBackup Server x.x Cluster Compatibility (updated date).
  - For x.x. look for the current release. For *date*, look for the most recent date.
- 5 Click the link for the PDF document.

# About configuring LiveUpdate with clustered NetBackup

Information is available on how to configure LiveUpdate to work with a clustered NetBackup server.

See the *Symantec NetBackup LiveUpdate Guide*.

#### About NetBackup limitations with clustering solutions

The following general limitations exist for NetBackup in a cluster:

- NetBackup does not support the conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.
- All NetBackup nodes must be running the same operating system and NetBackup version.

- NetBackup clustering does not support multiple master servers in a single cluster.
- NetBackup server clustering is not supported on UNIX and Linux platforms.
- NetBackup Enterprise Server is supported with all cluster solutions See "NetBackup supported cluster solutions" on page 13.
- Refer to the *Symantec NetBackup Release Notes* for limitations specific to NetBackup database agents and options. Refer to the Symantec NetBackup Administrator's Guide for limitations specific to Media Manager.

Chapter 2

# NetBackup in a Microsoft Cluster Server

This chapter includes the following topics:

- About NetBackup on Microsoft Cluster Server
- Installation prerequisites for NetBackup on MSCS cluster
- Installing a NetBackup failover server on MSCS cluster
- Configuring a NetBackup server on MSCS cluster
- Upgrading a NetBackup failover server on MSCS cluster
- Restoring the cluster quorum
- Restoring the cluster quorum to a node with directory services
- Preparation for disaster recovery of MSCS
- Disaster recovery of MSCS
- Recovering the entire MSCS cluster
- Recovering all shared disks
- About recovering NetBackup data on a shared disk

#### About NetBackup on Microsoft Cluster Server

Microsoft Cluster Server (MSCS) is a high-availability solution for cluster configurations. With Microsoft Cluster Server you can monitor systems and application services. Refer to the documentation for MSCS to get a detailed understanding of how MSCS works and how it is installed and administered.

For detailed information on how NetBackup is installed and administered, see the Symantec NetBackup Installation Guide and Symantec NetBackup Administrator's Guide. Volume I.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. For more information, refer to the Symantec NetBackup in Highly Available Environments Administrator's Guide.

#### Installation prerequisites for NetBackup on MSCS cluster

The following requirements must be met before you install and configure a NetBackup failover server in an MSCS environment:

 Verify that MSCS and NetBackup 7.5 support your hardware. For a list of supported storage devices, visit the following Web site. Also consult the MSCS documentation.

http://entsupport.symantec.com

- Verify that storage devices are properly installed and configured to work in a Windows environment. Refer to the information on configuring storage devices in the Symantec NetBackup Installation Guide.
- Verify that Microsoft Cluster Server is correctly installed and configured. (all versions are supported with NetBackup 7.5). NetBackup can be installed on as many nodes as MSCS supports. MSCS supports up to 4 or 8 nodes in a cluster, depending on the level of Windows that is installed.
- Physically connect the robotic devices and tape devices to each node where you want to install NetBackup). Connect devices by SCSI or Fibre Channel. Use OS commands to verify that all the devices are connected properly. See the Symantec NetBackup Device Configuration Guide.
- Verify that you have an IP address and host name (virtual name) to be assigned to the NetBackup cluster group. Use these only for the NetBackup cluster group.
  - Also, verify that the disk resource is online on the node from which the NetBackup installation is about to be performed for the first time on the cluster. With this release IPv6 is supported with NetBackup.
  - See "About NetBackup's IPv6 support" on page 97.
- Use Cluster Administrator to verify that the Possible Owners list for each disk resource that NetBackup uses includes each node to which NetBackup can failover.

- Verify that you have the NetBackup Enterprise Server 7.5 or NetBackup server 7.5 installation program and a valid license key.
- The Microsoft Cluster Administrator must be installed on all NetBackup servers that you use to administer the NetBackup failover master server remotely. Microsoft Cluster Administrator must also be installed on any NetBackup administration clients.
- You must have administrator rights or domain administrator credentials on the server cluster.
- On Windows, the public network names must be the same on both nodes of the cluster for push installs.
- You should install NetBackup on the same path on all the nodes.

# Installing a NetBackup failover server on MSCS cluster

Before you begin installation, review the following notes:

- These instructions assume that this installation is a new installation of a NetBackup failover server.
  - To upgrade NetBackup rather than complete an initial installation, follow the upgrade procedure.
  - See "Upgrading a NetBackup failover server on MSCS cluster" on page 21.
- You must install the same type of NetBackup server on each node to which NetBackup may failover.
- The virtual name cannot be more than 15 characters because of a Microsoft limitation.

Note: After you configure NetBackup as a cluster group in MSCS, do not change the group name.

The installation program does the following:

- Installs NetBackup on the node with shared disk resource online.
- Pushes the install to each inactive node, including the single license key you provided for a master server installation.
- Brings the NetBackup resources online.

To upgrade NetBackup rather than complete an initial installation, you follow a different procedure.

See "Upgrading a NetBackup failover server on MSCS cluster" on page 21.

#### To install a NetBackup failover server in an MSCS cluster

- Install NetBackup on all nodes of the cluster. This installation can be done in the following ways:
  - Install on the cluster node (with shared disk online) and push install to all other nodes in the cluster.

Or

■ Install on the cluster node (with shared disk online). After the first node installation, manually install on all other nodes in the cluster.

Follow the instructions for NetBackup in a clustered environment as described in the Symantec NetBackup Installation Guide.

- When you are prompted to provide the list of servers, enter all servers that need to have access to the NetBackup failover server.
- If you have added license keys at the end of the installation, failover and add these keys to each node in the cluster.

See "About adding license keys" on page 92.

- Install any agents or options that require separate installations.
  - Most Windows agents and options only require a special license key and do not require a separate installation. See the appropriate NetBackup documentation for the specific database agent or option for more information.
- After the installation is complete, continue with the configuration of NetBackup.

See "Configuring a NetBackup server on MSCS cluster" on page 20.

#### Configuring a NetBackup server on MSCS cluster

Do the following steps to configure NetBackup server in a cluster.

Table 2-1 Configuring a NetBackup server on MSCS cluster

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.

Table 2-1 Configuring a NetBackup server on MSCS cluster (continued)

Step	Action
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.
	Catalog backup information is stored on the shared disk and does not need to be configured for each node.
4	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.
	See "About configuring backup policies for a NetBackup clustered server" on page 87.
5	By default, NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail. You can configure NetBackup options to failover NetBackup if a service or the option fails.
	See "Configuring add-ons for monitoring (Windows)" on page 92.
6	When you have completed the configuration of NetBackup, verify that NetBackup can fail over properly in the cluster.
	See "Verifying NetBackup configuration" on page 89.

# **Upgrading a NetBackup failover server on MSCS** cluster

Follow these instructions if you want to upgrade from NetBackup 6.0 and later.

Note: NetBackup does not support conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.

#### To upgrade a NetBackup failover server on MSCS cluster

- Ensure that a good backup of your cluster environment exists that includes a catalog backup.
  - See "Configuring NetBackup catalog backups in a cluster" on page 86.
- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list should contain the name of each node where NetBackup can run and the name of the virtual server.
- Take all NetBackup resources offline except for the disk resource, virtual IP, and virtual name before you begin the upgrade install.
- Follow the instructions for how to upgrade NetBackup in a clustered environment as described in the Symantec NetBackup Installation Guide.

The installation program does the following:

- Upgrades NetBackup on the active node.
- Pushes the install to each inactive node.
- Brings the NetBackup resources online.
- Upgrade and configure any database agents or options.

Most agents and options require only a license key and do not need to be upgraded separately. For information on how to install and configure a specific agent or option, see the appropriate NetBackup documentation for that agent or option.

#### Restoring the cluster quorum

The cluster quorum is backed up as part of System State or Shadow Copy Components for each node. To restore the cluster quorum, other nodes in the cluster must be offline. If you cannot take the other nodes in the cluster offline before you restore the cluster quorum, follow the instructions in the next procedure.

#### To force the restore of the cluster quorum when other nodes are online

Create the following registry entry:

```
HKEY LOCAL MACHINE\Software\VERITAS\NetBackup\CurrentVersion\
Config\Cluster Database Force Restore
```

The actual registry entry must be on a single line. If required, create this registry value as data type REG SZ with a value of YES. When this value is set, the cluster service is stopped for any nodes that are online.

If Active Directory is running on the target server or the target server is currently a domain controller, the restore procedure is different.

See "Restoring the cluster quorum to a node with directory services" on page 24.

#### To restore the cluster quorum

- If the other nodes in the cluster are online, create the registry entry as described in the previous procedure.
- In the NetBackup Backup, Archive, and Restore interface, open a Restore window.
- Select the backup image (or range of images) that contains the backup of the **System State** or **Shadow Copy Components** for this node of the cluster.
- In the All Folders pane, select System State or Shadow Copy Components.
- If the disk where the cluster quorum previously resided is changed, set the registry entry. This action forces the restore to continue.

See "To force the restore of the cluster quorum when other nodes are online" on page 23.

The disk may have been replaced with a new one. Or the disk configuration may have been changed so that the cluster quorum now resides on a different disk. In the latter case, the drive letter can remain the same for the disk that contained the cluster quorum. The drive letter can remain the same even if the configuration has changed. It can also remain the same if the disk signatures in the restore media do not match the signatures in the cluster auorum.

- 6 Continue the restore.
- When the restore operation is complete, restart the cluster node. Or use the Microsoft Cluster Administrator to restart the cluster service on any nodes where it was stopped.

#### Restoring the cluster quorum to a node with directory services

To restore the quorum to a node that is either running Active Directory or that is currently a domain controller, the node must be in Directory Services Restore Mode. The cluster services cannot run in this mode. So the cluster quorum must be restored separately, after the System State or the Shadow Copy Components are restored and after the node is restarted.

#### To restore the cluster quorum to a node running Active Directory or that is currently a domain controller

- In the NetBackup Backup, Archive, and Restore interface, open a **Restore**
- Select the backup image (or range of images) that contains the backup you want to restore.
- Exclude the cluster quorum from the restore, as follows:
  - For Windows 2000, expand System\_State and then deselect Cluster Database.
  - For Windows 2003, expand Shadow Copy Components > System State and then deselect Cluster\_Quorum.
- 4 Continue the restore.
- When the restore operation is complete, restart the cluster node in Safe (repair) mode. Then select Directory Services Restore Mode.
- Start the NetBackup service(s). 6
- 7 Open the NetBackup Backup, Archive, and Restore interface.
- Select only the cluster quorum, as follows:
  - For Windows 2000, expand **System\_State** and select only Cluster\_Database.
  - For Windows 2003, expand **Shadow Copy Components > System State** and select only Cluster\_Quorum.

If the disk where the cluster quorum previously resided is changed, you may have to set the registry entry. This action forces the restore to continue.

See "To force the restore of the cluster quorum when other nodes are online" on page 23.

The disk may have been replaced with a new one. Or the disk configuration may have been changed so that the cluster quorum now resides on a different disk. In the latter case, the drive letter can remain the same for the disk that contained the cluster quorum. The drive letter can remain the same even if the configuration has changed. It can also remain the same if the disk signatures in the restore media do not match the signatures in the cluster quorum.

- **10** Continue the restore.
- 11 When the restore is complete, restart the target node.
- 12 Use Microsoft Cluster Administrator to restart the cluster service on any nodes where it was stopped.

# Preparation for disaster recovery of MSCS

For complete instructions on recovery of MSCS, refer to the following Microsoft Document. Symantec only provides instructions for how to restore the objects that you have backed up with NetBackup. Refer to Server Clusters: Backup and Recovery Best Practices for Windows Server 2003, which can be found on the Microsoft Web site:

www.microsoft.com/technet/prodtechnol/windowsserver2003/technologies/clustering/sercbr bp.mspx

# Disaster recovery of MSCS

Various disaster recovery scenarios are discussed in the following topics:

- See "Recovering the entire MSCS cluster" on page 26.
- See "Recovering all shared disks" on page 26.
- See "About recovering NetBackup data on a shared disk" on page 27. This last topic describes how to recover the shared disk where the NetBackup application resides.

#### Recovering the entire MSCS cluster

The following procedure describes how to recover the nodes in a cluster to their pre-disaster state.

#### To recover the entire MSCS cluster

- On the first node you want to recover, reinstall the Windows operating system, including the last service pack that was applied before the failure.
- 2 Install any other drivers or applications to make the node operational.
- After you start the nodes in a cluster, ensure that the drive letters match the original cluster configuration. If the original configuration does not match, you can use the Disk Administrator to control the hard drive numbering scheme of the Windows devices.
- On all remaining nodes you need to recover, reinstall Windows, including the last service pack that was applied before the failure.
- Reinstall the cluster services and bring the cluster online.
- Reinstall the same NetBackup software on the cluster that was installed before the failure.
- Use the appropriate NetBackup catalog recovery procedure to restore the NetBackup catalog information before continuing.
  - See the Symantec NetBackup Troubleshooting Guide for more information on recovering the NetBackup catalog database.
- If the clustered NetBackup server is a media server, verify that the restored vm.conf file contains the correct host-specific MM SERVER NAME configuration entry for the active node. If MM SERVER NAME is different from the local host name, server name to the local host name:
  - MM SERVER NAME=local host name
- Restore the data files through the virtual server.
- 10 If you must restore a database to the shared drives, see the Administrator's Guide for your database agent to continue the restore.

## Recovering all shared disks

The following procedure describes how to recover the shared disks in MSCS cluster.

#### To recover all shared disks

- 1 Uninstall the cluster software from both nodes.
- 2 Replace and repartition the shared disks.

- Reinstall the cluster software.
- 4 Ensure that all NetBackup shared disks are assigned the same drive letters that were used when NetBackup was originally installed and configured.
- To reconfigure NetBackup for the cluster, do the following on the active node:
  - Run the following command:

```
bpclusterutil -ci
```

- Recreate the database.
- Run the following commands:

```
tpext
bpclusterutil -online
```

- Use the appropriate NetBackup catalog recovery procedure to restore the NetBackup catalog information on the shared disk before continuing. See the Symantec NetBackup Troubleshooting Guide for more information on recovering the NetBackup catalog database.
- If the clustered NetBackup server is a media server, verify that the restored vm.conf file contains the correct host-specific MM SERVER NAME configuration entry for the active node. If MM SERVER NAME is different from the local host name, server name to the local host name:

```
MM SERVER NAME=local host name
```

Use NetBackup to restore any data on the shared disks. For details on how to perform a restore, see the NetBackup Backup, Archive, and Restore Getting Started Guide.

# About recovering NetBackup data on a shared disk

To recover the shared disk that the NetBackup failover server used, follow the appropriate NetBackup catalog recovery procedure to restore the catalog information on the shared disk.

If the clustered NetBackup server is a media server, verify that the restored vm.conf file contains the correct host-specific MM\_SERVER\_NAME configuration entry for the active node. If MM SERVER NAME is different from the local host name, server name to the local host name:

MM SERVER NAME=local host name

See the Symantec NetBackup Troubleshooting Guide for more information on recovering the NetBackup catalog database.

Chapter 3

# NetBackup in a Veritas Cluster Server on UNIX/Linux

This chapter includes the following topics:

- About NetBackup on a Veritas Cluster Server on UNIX/Linux
- Installation prerequisites for NetBackup on VCS on UNIX/Linux
- About preinstallation checklist for a NetBackup failover server installation on VCS on Unix\Linux
- Installing a failover NetBackup server on VCS on UNIX/Linux
- Configuring a failover NetBackup server on VCS on UNIX/Linux
- About adding a node to existing cluster
- Installing or upgrading NetBackup database agents and options on VCS on UNIX/Linux
- Upgrading a NetBackup failover server on VCS on Unix/Linux

# About NetBackup on a Veritas Cluster Server on UNIX/Linux

Veritas Cluster Server (VCS) is a high-availability solution for cluster configurations. VCS enables you to monitor systems and application services and to restart services on a different system when hardware or software fails.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. Refer to the Symantec NetBackup in Highly Available Environments Administrator's Guide for more information.

NetBackup supports the use of the Global Cluster Option (GCO) with VCS. For information on how to configure and use GCO with NetBackup, refer to Symantec NetBackup in Highly Available Environments Administrator's Guide.

# Installation prerequisites for NetBackup on VCS on **UNIX/Linux**

The following requirements must be met before you install and configure a NetBackup failover server:

- Verify that VCS and NetBackup Enterprise Server 7.5 support your hardware. For a list of supported storage devices, visit the following Web site: http://entsupport.symantec.com
- Verify that the supported version of VCS is correctly installed and configured on Solaris, HP-UX, AIX, or Linux. Follow the steps in the Veritas Cluster Server Installation Guide.
- Verify that no VCS resource group and resource exist with the same name as the one you intend to use for NetBackup.
- Make sure that the shared disk is configured and accessible to all cluster nodes where you want to install NetBackup. Also, verify that you can mount the disk.
- Verify that you have an IP address (virtual IP) and a host name (virtual name) to assign to the NetBackup resource in VCS. Use these only for the NetBackup resource.
  - Also, ping the IP address and verify that the IP address is not plumbed. For VCS-UNIX, IP address of the Nodes and Virtual Name must be of same type (IPv6 or IPv4).
  - With this release IPv6 is supported with NetBackup. See "About NetBackup's IPv6 support" on page 97.
- Make sure that each node in the cluster, where you want to install NetBackup, is RSH equivalent (On HP Service Guard the command is remsh). As the root user you must be able to perform a remote logon to each node in the cluster without entering a password. This configuration is only necessary for installation, upgrades, and configuration of the NetBackup server and any NetBackup database agents and options. After installation and configuration are complete RSH can be disabled.

**Note:** Node IP type must be same as virtual IP type.

- For a clustered NetBackup master server, if the master server is the robotic control host, physically connect the robotic devices and tape devices to each node where you want to install NetBackup. Connect devices by SCSI or Fibre Channel. Use OS commands to verify that all the devices are connected properly. Refer to the Symantec NetBackup Device Configuration Guide.
- Verify that you have the NetBackup Enterprise Server 7.5 installation program and a valid license key.

# About preinstallation checklist for a NetBackup failover server installation on VCS on Unix\Linux

The NetBackup Enterprise Server requests certain cluster-related information during installation. Fill up the checklist for all configurations and the checklist for your specific configuration before you begin installation.

See "NetBackup installation information for all VCS configurations" on page 31.

See "NetBackup installation information for specific VCS configurations" on page 32.

Note: The configuration utility unless specified otherwise treats all attribute values globally.

#### NetBackup installation information for all VCS configurations

The following information is required for all VCS cluster configurations:

- Virtual name for NetBackup
- IP address
- Subnet mask or Prefix length
- Node name

Following information is required for each node:

- IP address
- Network device name (NIC)

#### NetBackup installation information for specific VCS configurations

The following information is required if you use VCS. Review the scenario that fits your configuration.

Scenario 1 - VCS with VxVM Table 3-1

Resource	Example
Disk group Resource	
Disk group	nbudg
Start Volumes	0 or 1
Stop Volumes	0 or 1
Volume Resource (optional)	
Volume	nbuvol
Mount Resource	
Mount Point	/opt/VRTSnbu
Block Device	/dev/vx/dsk/nbudg/nbuvol
FS Type	vxfs
Mount Option	(optional)
Fsck Option	(if you add other options, -y is also required)

Table 3-2 Scenario 2- VCS with no Volume Manager

Resource	Example
Mount Point	/opt/VRTSnbu
Block Device	/dev/dsk/clt1dos3
FS Type	vxfs
Mount Option	(optional)
Fsck Option	(if you add other options, -y is also required)

Table 3-3 VCS with AIX LVMVG

Resource	Example
Volume Group	nbuvg
Major Number	58
Disks	hdisk1 or hdisk2
ImportvgOpt	(optional)
VaryonvgOpt	(optional)
SyncODM	(optional)
Mount Resource	
Mount Point	/opt/VRTSnbu
Block Device	/dev/nbudev
FS Type	jfs2
Mount Option	(optional)
Fsck Option	(if you add other options, -y is also required)

Table 3-4 Scenario 4 - VCS in HP-UX with logical volume manager

Resource	Example
LVM Volume Group Resource	
Volume Group	vg0a
LVM Logical Volume Resource	
Volume Group	vg0a
Logical Group	lvol1

# Installing a failover NetBackup server on VCS on **UNIX/Linux**

This topic describes how to install and configure a new NetBackup Enterprise Server as a failover application on a VCS on UNIX or Linux. To upgrade NetBackup, you must follow a different procedure.

See "Upgrading a NetBackup failover server on VCS on Unix/Linux" on page 37.

Note: You must install the NetBackup master server on each node to which NetBackup may failover. You cannot have a separate failover master server in your NetBackup configuration.

The following procedure describes how to install and configure a NetBackup failover server in a VCS cluster.

Note: NetBackup automatically detects supported clustering technology and prompts questions based on it. If you are not prompted for these questions on a clustered setup, please exit from the script and verify that cluster is configured correctly. Refer to the cluster guide for details on how to verify the cluster setup.

#### To install a NetBackup failover server

Fill out the checklist for all configurations and the checklist for your specific environment.

See "NetBackup installation information for all VCS configurations" on page 31.

See "About preinstallation checklist for a NetBackup failover server installation on VCS on Unix\Linux" on page 31.

- Make sure that the shared disk is not mounted on any node in the cluster.
  - If applicable, unmount the NetBackup shared mount point. Stop the volume the mount point is on and deport the disk group for that volume on all nodes of the cluster.
- Follow the instructions for how to install NetBackup in the Symantec NetBackup Installation Guide.

Be sure that you:

- Install NetBackup on each node to which it can failover.
- Use the virtual name for the NetBackup server name.

Caution: When you are prompted, you must provide the same virtual cluster name that you provided during the installation. This name is case-sensitive and must be in same format (FQDN/short) on all the nodes.

When NetBackup is installed on the clustered setup a confirmation prompt is displayed.

- When you install NetBackup on the first node, you are prompted to confirm creation of a NetBackup cluster. Type **Yes** to set up NetBackup in HA mode.
- When you install NetBackup on the subsequent nodes, information about already created NetBackup cluster group is displayed. You are prompted to join the group.
- When you are prompted for cluster-specific configuration details, refer to the checklist and provide details accordingly.
- Allow NetBackup to be installed in a cluster. When a NetBackup failover server is installed:
  - On the first node, a single node cluster resource group for NetBackup is created and brought online.
  - On the other nodes, the installed node is added to the cluster resource group.
- Install any NetBackup database agents or options.
  - See "Installing or upgrading NetBackup database agents and options on VCS on UNIX/Linux" on page 36.
- Continue with configuration of NetBackup.See "Configuring a failover NetBackup server on VCS on UNIX/Linux" on page 35.

# Configuring a failover NetBackup server on VCS on **UNIX/Linux**

To configure NetBackup server in a cluster, do the following:

Table 3-5 Configuring a failover NetBackup server on VCS on UNIX/Linux

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.

Table 3-5 Configuring a failover NetBackup server on VCS on UNIX/Linux (continued)

Step	Action
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.
	Catalog backup information is stored on the shared disk and does not need to be configured for each node.
4	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.
	See "About configuring backup policies for a NetBackup clustered server" on page 87.
5	When you have completed configuration of NetBackup, verify that NetBackup can failover properly in the cluster.
	See "Verifying NetBackup configuration" on page 89.

#### About adding a node to existing cluster

To add a node to the existing cluster, add the node to the VCS cluster before NetBackup is installed. The installer automatically detects the new node and adds it to the NetBackup cluster configuration.

# Installing or upgrading NetBackup database agents and options on VCS on UNIX/Linux

Install or upgrade NetBackup database agents and options on all cluster nodes where the NetBackup server is installed. In addition, the NetBackup group must be frozen before you install any agents or options.

**Note:** Before you upgrade any database agents or options, ensure that the NetBackup resource is online in the cluster. Also ensure that server processes are running on the active node.

#### To install or upgrade a NetBackup agent or option on VCS on UNIX/Linux

- Enable the VCS configuration in read and write mode with haconf -makerw
- Freeze the NetBackup group with  $hagrp freeze nbu\_group\_name$ -persistent.

Run the following command on the active node to disable the NetBackup agent monitor:

touch /usr/openv/netbackup/bin/cluster/frozen

- On each inactive node in the cluster where NetBackup is installed, install any agents or options. See the appropriate NetBackup documentation for the agent or option for installation and configuration instructions.
- On the active node, perform the same installation.
- Unfreeze the NetBackup group with hagrp -unfreeze nbu group name -persistent
- 7 Enable the VCS configuration in read-only mode with haconf -dump -makero
- Run the following command on the active node to enable the NetBackup agent monitor:

rm -f /usr/openv/netbackup/bin/cluster/frozen

(Optional) Configure robot daemons and NetBackup options to failover NetBackup if a daemon or the option fails. By default, robotic daemons and NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail.

See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.

See "Configuring add-ons for monitoring (UNIX/Linux clusters)" on page 91.

## Upgrading a NetBackup failover server on VCS on Unix/Linux

Follow these instructions if you want to upgrade from NetBackup 6.0 or later.

**Note:** NetBackup does not support conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.

Note: Symantec requires that you use the latest VCS agent that is installed with NetBackup 7.5. Older versions of the agent are not supported.

#### To upgrade a NetBackup failover server

Ensure that a good backup of your cluster environment exists that includes a catalog backup.

See "Configuring NetBackup catalog backups in a cluster" on page 86.

- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list should contain the name of each node where NetBackup can run and the name of the virtual server.
- Take the VCS NetBackup cluster resource offline before you begin the upgrade.

Note: Make sure that shared disk and IP resources are online during the upgrade on active node.

- Enable the VCS configuration in read and write mode with haconf -makerw 4
- Freeze the NetBackup group using the following command:

```
hagrp -freeze <nbu group name> -persistent
```

Stop the NetBackup cluster agent on all nodes of the NetBackup Group using the following command:

```
haagent -stop NetBackup -force -sys < node>
```

On the active node, install the NetBackup server software.

#### Note the following:

- Follow the instructions for how to upgrade NetBackup as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.
- On each inactive node to which NetBackup may failover, install the NetBackup server software.

#### Note the following:

- Follow the instructions for how to upgrade NetBackup as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.

Start the VCS NetBackup cluster agent on all nodes of the NetBackup Group. Use the following command:

```
haagent -start NetBackup -sys <node>
```

- 10 Enable the VCS configuration in read and write mode with haconf -makerw
- 11 Unfreeze the NetBackup group using the following command:

```
hagrp -unfreeze <nbu group name> -persistent
```

- 12 Enable the VCS configuration in read-only mode with haconf -dump -makero
- 13 Take the NetBackup group offline and then bring online.
- **14** On each node where NetBackup server is installed, upgrade any NetBackup database agents or options.
  - See "Installing or upgrading NetBackup database agents and options on VCS on UNIX/Linux" on page 36.
- **15** Verify that NetBackup can failover properly in the cluster.

See "Verifying NetBackup configuration" on page 89.

Note: During freezing or unfreezing the groups, make sure that the status of configuration is in Read-Write mode.

Chapter 4

# NetBackup in a Veritas Cluster Server on Windows

This chapter includes the following topics:

- About NetBackup in a Veritas Cluster Server on Windows
- About NetBackup agent for VCS on Windows
- Installation prerequisites for NetBackup on VCS on Windows
- Installing a NetBackup failover server on VCS on Windows
- Configuring a NetBackup server on VCS on Windows
- Upgrading a NetBackup failover server on VCS on Windows
- About detailed monitoring for the NetBackup server
- Setting up a detailed monitoring script for the NetBackup server on VCS on Windows
- Enabling detailed monitoring in VCS Cluster Manager for the NetBackup server
- Disabling detailed monitoring in VCS Cluster Manager for the NetBackup server

# About NetBackup in a Veritas Cluster Server on Windows

Veritas Cluster Server(VCS) is a high-availability solution for cluster configurations. With VCS you can monitor systems and application services, and restart services on a different system when hardware or software fails. For information about VCS, refer to the *Veritas Cluster Server Administrator's Guide*.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. Refer to the Symantec NetBackup in Highly Available Environments Administrator's Guide for more information.

#### About NetBackup agent for VCS on Windows

The NetBackup agent for VCS monitors specific NetBackup resources, determines the status of these resources, and starts or stops NetBackup according to external events. The agent includes VCS type declarations and agent executables. The NetBackup resource type represents the agent. When the agent detects an application failure, the NetBackup service group is failed over to another system in the cluster. NetBackup is installed and configured on this stem.

The following table describes the specific agent operations.

Online Brings the NetBackup services online.

Offline Takes the NetBackup services offline.

Monitor Verifies the status of NetBackup services. Detailed monitoring is also

available.

See "Setting up a detailed monitoring script for the NetBackup server

on VCS on Windows" on page 47.

Clean Stops all NetBackup daemons if there is a detection of an unexpected

offline operation or an ineffective online operation.

Additional monitoring capabilities are available for add-on products.

See "Configuring add-ons for monitoring (Windows)" on page 92.

NetBackup supports the use of the Global Cluster Option (GCO) with VCS. For information on how to configure and use GCO with NetBackup, refer to Symantec NetBackup in Highly Available Environments Administrator's Guide.

#### Installation prerequisites for NetBackup on VCS on Windows

The following requirements must be met before you install and configure a NetBackup failover server:

■ Verify that VCS and NetBackup 7.5 support your hardware. For a list of supported storage devices, visit the following Web site: http://entsupport.symantec.com

- Verify that storage devices have been properly installed and configured to work in a Windows environment. Refer to the section on how to configure storage devices in the Symantec NetBackup Installation Guide.
- Verify that you have installed Veritas Storage Foundation HA and correctly configured VCS. NetBackup can be installed on as many nodes as VCS supports. The NetBackup service group is created during the installation.
- For VCS Windows (SFW-HA 4.1, SFW-HA 4.2, SFW-HA 6) make sure the patch available through Technote 278307 is installed before you install or upgrade to NetBackup 7.5. The patch is available at the following Web site: http://entsupport.symantec.com/docs/278307.

Note: In few cases, after the NetBackup master cluster installation, the resource is not installed into the service group. In case the resource of type "NetBackupVCS" is added manually, the attributes of NetBackupVCS are blank and this resource cannot probe on cluster servers. For work-around, refer Technote 174147.

- Verify the cluster disk group(s) and dynamic volume(s) for NetBackup have been created on the shared storage. Refer to the Veritas Storage Foundation Administrator's Guide for details on how to create these.
- All disk resources that you want NetBackup to use must be configured in Veritas Enterprise Administrator (VEA) before you install NetBackup.
- Verify that you have an IP address and host name (virtual name) to be assigned to the NetBackup resource in VCS. Only use these for the NetBackup cluster group. The virtual name cannot be more than 15 characters. Also, verify that the disk resource is online on the node from which the NetBackup installation is about to be performed for the first time on the cluster.
- For a clustered NetBackup master server, if the master server is the robotic control host, physically connect the robotic devices and tape devices to each node where you want to install NetBackup. Connect devices by SCSI or Fibre Channel. Use OS commands to verify that all the devices are connected properly. Refer to the Symantec NetBackup Device Configuration Guide.
- Verify that you have the NetBackup Enterprise Server 7.5 or NetBackup server 7.5 installation program and a valid license key.
- On Windows, the public network names must be same on both nodes of the cluster for push-installs.
- You should install NetBackup on the same path on all nodes.

#### Installing a NetBackup failover server on VCS on Windows

This section describes how to install and configure a new NetBackup Enterprise Server as a failover application in a VCS for Windows cluster. If you want to upgrade NetBackup, rather than complete an initial installation, you must follow a different procedure.

See "Upgrading a NetBackup failover server on VCS on Windows" on page 46.

Review the following notes before you begin installation:

- These instructions assume that this installation is a new installation of a NetBackup failover server.
- You must install the same type of NetBackup server on each node to which NetBackup may failover. You cannot have a separate failover master server and a separate failover media server in your NetBackup configuration.
- After you configure NetBackup as a cluster group in VCS, do not change the group name.
- The virtual name cannot be more than 15 characters.

The installation program does the following:

- Installs NetBackup on the active node.
- Pushes the install to each inactive node, including the single license key you provided for the master server.
- Brings the NetBackup resources online.

The following procedure describes how to install a NetBackup failover server in a VCS cluster.

#### To install a NetBackup failover server on a VCS cluster

- Install NetBackup on all nodes of the cluster. This installation can be done in the following ways:
  - Install on the cluster node (with shared disk online) and push install to all other nodes in the cluster.

Or

■ Install on the cluster node (with shared disk online). After the first node installation, manually install on all other nodes in the cluster.

- Follow the instructions for how to install NetBackup in a clustered environment as described in the Symantec NetBackup Installation Guide.
- When you are prompted to provide the list of servers, enter all servers that must have access to the NetBackup failover server.
- If you added license keys at the end of the installation, fail over and add these keys to each node in the cluster.
  - See "About adding license keys" on page 92.
- Install any agents or options that require separate installations.
  - Most Windows agents and options only require a special license key and do not require a separate installation. See the appropriate NetBackup documentation for the specific database agent or option for more information.
- After the installation is complete, continue with the configuration of NetBackup.See "Configuring a NetBackup server on VCS on Windows" on page 45.

## Configuring a NetBackup server on VCS on Windows

Do the following steps to configure NetBackup server on a VCS cluster on Windows.

Table 4-1 Configuring a NetBackup server on VCS on Windows

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.

Configuring a NetBackup server on VCS on Windows (continued) Table 4-1

Step	Action
4	Catalog backup information is stored on the shared disk and does not need to be configured for each node.
	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.
	See "About configuring backup policies for a NetBackup clustered server" on page 87.
5	By default, NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail. You can configure NetBackup options to failover NetBackup if a service or the option fails.
	See "Configuring add-ons for monitoring (Windows)" on page 92.
6	When you have completed the installation and configuration of NetBackup, verify that NetBackup can fail over properly in the cluster.
	See "Verifying NetBackup configuration" on page 89.

## Upgrading a NetBackup failover server on VCS on **Windows**

Follow these instructions if you want to upgrade from NetBackup 6.0 or later.

Note: NetBackup does not support conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.

#### To upgrade a NetBackup failover server

- Ensure that a good backup of your cluster environment exists that includes a catalog backup.
  - See "Configuring NetBackup catalog backups in a cluster" on page 86.
- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list should contain the name of each node where NetBackup can run and the name of the virtual server.
- Take the VCS NetBackup resource offline before you begin the upgrade.

Note: Make sure that shared disk and IP resources are online during the upgrade on active node.

Follow the instructions for how to upgrade NetBackup as described in the Symantec NetBackup Installation Guide.

The installation program does the following:

- Upgrades NetBackup on the active node.
- Pushes the install to each inactive node.
- Brings online all the NetBackup resources.
- Upgrade and configure any database agents or options.

Most agents and options require only a license key and do not need to be upgraded separately. For information on how to install and configure a specific agent or option, see the appropriate NetBackup documentation for that agent or option.

**Note:** When you upgrade NetBackup on cluster, NetBackup resource goes into faulted state. You must clear the fault after upgrade is complete.

#### About detailed monitoring for the NetBackup server

In the detail monitoring mode, the NetBackup agent runs a script to verify that NetBackup is available. A sample script, DetailedMonitor.bat, is provided with the agent for this purpose. You can customize the script to meet your configuration requirements.

Note: Before setting up detailed monitoring, the NetBackup agent must run base level of monitoring.

## Setting up a detailed monitoring script for the NetBackup server on VCS on Windows

This topic describes how to set up detailed monitoring for a NetBackup server that is installed in a VCS for Windows environment. The script file must exist on all nodes in the service group's system list.

#### To set up a detailed monitoring script for the NetBackup server on VCS on Windows

- Configure and run the NetBackup agent with the basic monitoring.
- For each node in the NetBackup service group, create a backup policy that performs a user backup of the file

install path\bin\cluster\VCS\DetailedMonitor.txt.

*install path* is the home directory of NetBackup.

For example, C:\Program Files\VERITAS\NetBackup

For example, if your NetBackup service group contains five nodes, you must create five different policies, each referencing a different node.

Make a copy of following file and edit it to fit your configuration.

install path\bin\cluster\DetailedMonitor.bat

- Replace VIRTSRVR with the virtual server name for the NetBackup master or media server.
- Make any other edits necessary.
- **4** From the command line, type the following command to verify the script runs without errors:

DetailedMonitorProd

Continue with the following topic to enable detailed monitoring:

See "Enabling detailed monitoring in VCS Cluster Manager for the NetBackup server" on page 48.

## **Enabling detailed monitoring in VCS Cluster Manager** for the NetBackup server

This topic describes how to set the detail monitoring option for the NetBackup server from the VCS Cluster Manager.

#### To enable detailed monitoring in VCS Cluster Manager for the NetBackup server

- In Cluster Explorer, right-click the NetBackup service group, choose **Offline**, and select the node where you want to bring the service group offline.
- 2 Click Yes.
- In the left pane, click the NetBackup resource.
- On the **Properties** tab, select the Monscript attribute from the list, and click Edit.

- Provide the full path to the NetBackup monitor script that you created. See "About detailed monitoring for the NetBackup server" on page 47.
- Click OK. 6
- 7 Save your configuration.
- In the left pane, right-click the NetBackup service group, select **Online**, and select the node where you want to bring the service group online.
- 9 Click Yes.

## Disabling detailed monitoring in VCS Cluster Manager for the NetBackup server

This section describes how to disable the detail monitoring option for the NetBackup server from the VCS Cluster Manager.

#### To disable detailed monitoring in VCS Cluster Manager for the NetBackup server

- In Cluster Explorer, right-click on the NetBackup service group, choose **Offline**, and select the node where you want to bring the service group offline.
- 2 Click Yes.
- In the left pane, click the NetBackup resource.
- On the **Properties** tab, select the **Monscript** attribute from the list, and click Edit.
- Remove the path information. 5
- 6 Click OK.
- 7 Save your configuration.
- In the left pane, right-click the NetBackup service group, select Online, and select the node where you want to bring the service group online.
- Click **Yes**.

50 NetBackup in a Veritas Cluster Server on Windows

Disabling detailed monitoring in VCS Cluster Manager for the NetBackup server

Chapter 5

# NetBackup in a SunCluster

This chapter includes the following topics:

- About NetBackup on SunCluster
- Installation prerequisites for NetBackup on SunCluster
- Preinstallation checklist for a NetBackup failover server installation on SunCluster
- Installing NetBackup on SunCluster
- Configuring NetBackup on SunCluster
- Installing or upgrading NetBackup database agents and options on SunCluster
- Upgrading a NetBackup failover server on SunCluster
- SunCluster commands for bringing the resource group online or offline

#### About NetBackup on SunCluster

NetBackup supports the HA Storage Plus option for Sun Clusters. Refer to the *Symantec NetBackup Administrator's Guide, Volume I*, for a detailed understanding of how NetBackup is installed and administered. Refer to the documentation for SunCluster for a detailed understanding of how SunCluster works and how it is installed and administered. This guide also includes information on the SunPlex cluster system.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. Refer to the *Symantec NetBackup in Highly Available Environments Administrator's Guide* for more information.

#### Installation prerequisites for NetBackup on SunCluster

This topic contains information about the requirements that must be met before you install and configure a NetBackup failover server in a SunCluster environment.

Type	of	prerequisite
·ypc	٠.	prerequisite

#### Description

#### General prerequisites

The following prerequisites apply to both types of SunCluster installations, HA Storage Plus, and Global File System.

■ Verify SunCluster and NetBackup Enterprise Server 7.5 support your hardware. For a list of supported storage devices, visit the following Web site. Also consult the SunCluster documentation.

http://entsupport.symantec.com

- Verify that you have an IP address and host name (virtual name) to be assigned to the NetBackup resource group. Only use these for the NetBackup resource group.
- Physically connect the robotic devices and tape devices to each node where you want to install NetBackup). Connect devices by SCSI or Fibre Channel . Use OS commands to verify that all the devices are connected properly. Refer to the Symantec NetBackup Device Configuration Guide.
- Make sure that each node in the cluster, where you want to install NetBackup, is RSH equivalent. As the root user you must be able to perform a remote logon to each node in the cluster without entering a password. This configuration is only necessary for installation, upgrades, and configuration of the NetBackup server and any NetBackup database agents and options. After installation and configuration are complete, RSH can be disabled.
- Verify that you have the NetBackup Enterprise Server 7.5 installation program and a valid license key.

#### HA Storage Plus prerequisites

The following prerequisites must be met for HA Storage Plus:

- Make sure that the disk has enough space for the NetBackup database files and directories.
- Mount the disk on the computer that you want to configure NetBackup on.

Type of prerequisite	Description
Global File System prerequisites	The following prerequisites must be met for Global File System:
	<ul> <li>The shared disk must be configured and accessible to all cluster nodes where you want to install NetBackup. See the SunCluster documentation for more information on how to create and configure a shared disk.</li> <li>Make sure that the shared disk has enough space for the NetBackup database files and directories.</li> <li>You must be able to mount the disk on all nodes at the same time.</li> </ul>

## Preinstallation checklist for a NetBackup failover server installation on SunCluster

The following information is required for SunCluster cluster configurations.

Resource	Example
Virtual name for NetBackup:	vname
Mount Point (Shared Directory Path):	/opt/VRTSnbu
HAStoragePlus Resource for NetBackup Data	y or n

## Installing NetBackup on SunCluster

This topic describes how to install a new NetBackup Enterprise Server as a failover application in a SunCluster. If you want to upgrade NetBackup, rather than complete an initial installation, you must follow a different procedure.

See "Upgrading a NetBackup failover server on SunCluster" on page 57.

Review the following notes before you begin installation:

- These instructions assume that this installation is a new installation of a NetBackup failover server.
- The NetBackup resource group name in a SunCluster is always scnb-harg. The user cannot configure this name.
- Two SunCluster resource files are installed with NetBackup and should not be edited: scnb. VRTS and scnb. conf.

Note: Cluster configuration is performed along with the installation process. Do not run the cluster config script to perform cluster configuration.

The following procedure describes how to install and configure a NetBackup failover server in a SunCluster.

**Note:** Additional commands are required to properly freeze and unfreeze NetBackup in a SunCluster, due to Sun bug #5017826. When NetBackup is started under pmf with automatic restarts enabled, pmf intervenes if the tag dies. This intervention happens whether the monitor is enabled or not.

**Note:** If the shared disk is a raw disk with Global File System (GFS) and the primary (active) node is turned off, the shared disk is not accessible from any of the remaining nodes. As a result, the NetBackup server fails to come online on any other node.

#### To install NetBackup on SunCluster

- Fill out the checklist for all configurations and the checklist for your specific environment.
  - See "Preinstallation checklist for a NetBackup failover server installation on SunCluster" on page 53.
- Follow the instructions for how to install NetBackup in the Symantec NetBackup Installation Guide.

Be sure that you:

- Install NetBackup on each node to which it can failover.
- Use the virtual name for the NetBackup server name.

Caution: When you are prompted, you must provide the same virtual cluster name that you provided during the installation. This name is case-sensitive and must be in same format (FQDN/short) on all the nodes.

- When NetBackup is installed on the clustered setup a confirmation prompt is displayed.
  - When you install NetBackup on the first node, you are prompted to confirm creation of a NetBackup cluster. Type Yes to set up NetBackup in HA mode.

- When you install NetBackup on the subsequent nodes, information of already created NetBackup cluster group is displayed. You are prompted to join the group.
- When you are prompted for cluster-specific configuration details, refer to the checklist and provide details accordingly.
- Allow NetBackup to be installed in a cluster. When a NetBackup failover server is installed:
  - On the first node, a single node cluster resource group for NetBackup is created and brought online.
  - On the other nodes, the installed node is added to the cluster resource group.
- Install any NetBackup database agents or options.
  - You must freeze the NetBackup group before you install any agents or options.
  - See "Installing or upgrading NetBackup database agents and options on SunCluster" on page 56.
- Continue with the configuration of NetBackup. See "Configuring NetBackup on SunCluster" on page 55.

## Configuring NetBackup on SunCluster

To configure NetBackup server in a cluster, do the following:

Table 5-1 Configuring NetBackup on SunCluster

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.
	Catalog backup information is stored on the shared disk and does not need to be configured for each node.

Step	Action
4	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.
	See "About configuring backup policies for a NetBackup clustered server" on page 87.
5	When you have completed configuration of NetBackup, verify that NetBackup can fail over properly in the cluster.
	See "Verifying NetBackup configuration" on page 89.

Table 5-1 Configuring NetBackup on SunCluster (continued)

## Installing or upgrading NetBackup database agents and options on SunCluster

To install or upgrade database agents and options, NetBackup daemons must be brought offline without causing a failover. SunCluster must be configured to stop monitoring NetBackup, but keep NetBackup resources online.

By default, robotic daemons and NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail. You can configure robot daemons and NetBackup options to failover NetBackup if a daemon or the option fails.

See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.

See "Configuring add-ons for monitoring (UNIX/Linux clusters)" on page 91.

#### To install or upgrade NetBackup database agents and options

Freeze the NetBackup group by executing the following:

```
/usr/cluster/bin/scswitch -n -j scnb-hars
```

Run the following command on the active node to disable the NetBackup agent monitor:

```
touch /usr/openv/netbackup/bin/cluster/frozen
```

- On active node, install or upgrade any database agents or options. See the appropriate NetBackup documentation for the agent or option for installation and configuration instructions.
- On the inactive node, perform the same installation.

After you complete the installations of any agents or options, run the following commands:

```
/usr/cluster/bin/scswitch -e -j scnb-hars
```

Run the following command on the active node to enable the NetBackup agent monitor:

```
rm -f /usr/openv/netbackup/bin/cluster/frozen
```

The NetBackup resources are brought online and SunCluster resumes monitoring the NetBackup resource.

## Upgrading a NetBackup failover server on SunCluster

Follow these instructions if you want to upgrade from NetBackup 6.0 and later. You must also have the SunCluster agent that was installed with your previous version of NetBackup.

**Note:** NetBackup does not support conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.

#### To upgrade a NetBackup failover server on SunCluster

Ensure that a good backup of your cluster environment exists that includes a catalog backup.

```
See "Configuring NetBackup catalog backups in a cluster" on page 86.
```

- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list should contain the name of each node where NetBackup can run and the name of the virtual server.
- Put NetBackup in the unmanaged state by executing the following commands:

```
/usr/cluster/bin/scswitch -n -j scnb-hars
```

On active node, install the NetBackup server.

Note the following:

- Follow the instructions for how to install NetBackup server as described in the *Symantec NetBackup Installation Guide*.
- If required to specify the server name, provide the virtual name of the server.

On each inactive node to which NetBackup may failover, install the NetBackup server.

Note the following:

- Follow the instructions for how to install NetBackup server as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.
- Run the following commands:

```
/usr/cluster/bin/scswitch -e -j scnb-hars
```

The NetBackup resources are brought online and SunCluster resumes monitoring the NetBackup resource.

- Bring the NetBackup resource group offline and online.
- On each node where NetBackup server is installed, upgrade any NetBackup database agents or options.

You must freeze the NetBackup group before you install any agents or options.

See "Installing or upgrading NetBackup database agents and options on SunCluster" on page 56.

Verify that NetBackup can failover properly in the cluster.

See "Verifying NetBackup configuration" on page 89.

## SunCluster commands for bringing the resource group online or offline

To bring the NetBackup resource group online or offline, special SunCluster commands must be used. See the SunCluster documentation for more information on these and other commands.

Table 5-2 describes the commands you use to bring the NetBackup resource group online or offline.

SunCluster commands Table 5-2

Action	Enter this command
To bring the NetBackup resource group online	/usr/cluster/bin/scswitch -z -g scnb-harg -h hostname

Table 5-2 SunCluster commands (continued)

Action	Enter this command
To bring the NetBackup resource group offline	/usr/cluster/bin/scswitch -F -g scnb-harg
To verify that the NetBackup resource is online	/usr/cluster/bin/scstat -g

Chapter 6

# NetBackup on HP Service Guard cluster

This chapter includes the following topics:

- About NetBackup on HP Service Guard cluster
- Installation prerequisites for NetBackup on HP Service Guard cluster
- Preinstallation checklist for a NetBackup failover server installation on HP Service Guard cluster
- Installing NetBackup on HP Service Guard cluster
- Configuring NetBackup on HP Service Guard cluster
- Installing or upgrading NetBackup database agents and options on HP Service Guard Cluster
- Upgrading a NetBackup failover server on HP Service Guard Cluster
- Service Guard commands for bringing the resource group online or offline

#### About NetBackup on HP Service Guard cluster

HP Service Guard is a high-availability solution for cluster configurations. With HP Service Guard you can monitor systems and application services, and restart services on a different system when hardware or software fails. Refer to the documentation for Service Guard for a detailed understanding of how Service Guard works and how it is installed and administered.

Refer to the *Symantec NetBackup Administrator's Guide, Volume I*, for a detailed understanding of how NetBackup is installed and administered.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. Refer to the Symantec NetBackup in Highly Available Environments Administrator's Guide for more information.

## Installation prerequisites for NetBackup on HP Service Guard cluster

The following requirements must be met before you install and configure a NetBackup failover server in a Service Guard environment:

- Verify Service Guard and NetBackup Enterprise Server 7.5 support your hardware. For a list of supported storage devices, visit the following Web site. Also consult the Service Guard documentation. http://entsupport.symantec.com
- Verify that the supported version of Service Guard is correctly installed and configured.
- Verify that you have an IP address and host name (virtual name) to be assigned exclusively to the NetBackup resource. With this release IPv6 is supported with NetBackup.
  - See "About NetBackup's IPv6 support" on page 97.
- The shared disk must be configured and accessible to all cluster nodes where you want to install NetBackup. See the Service Guard and the appropriate Volume Manager (Veritas or HP) documentation for more information on how to create and configure a shared disk. Make sure that the shared disk has enough space for the NetBackup database files and directories. Make sure that the disk is not mounted on any system and that all volume groups are offline and volumes are stopped before installing NetBackup.
- You can have the database spread across multiple shared disks for performance reasons. This configuration can be performed after the initial cluster configuration.
- Physically connect the robotic devices and tape devices to each node where vou want to install NetBackup. Connect devices by SCSI or Fibre Channel, Use OS commands to verify that all the devices are connected properly. Refer to the Symantec NetBackup Device Configuration Guide.
- Make sure that each node in the cluster, where you want to install NetBackup, is remsh equivalent. As the root user you need to be able to perform a remote logon to each node in the cluster without entering a password. This configuration is only necessary for installation, upgrades, and configuration

of the NetBackup server and any NetBackup database agents and options. After installation and configuration are complete, remsh can be disabled.

■ Verify that you have the NetBackup Enterprise Server 7.5 installation program and a valid license kev.

## Preinstallation checklist for a NetBackup failover server installation on HP Service Guard cluster

The NetBackup Enterprise Server requests certain cluster-related information during installation. Fill out the checklist for all configurations and the checklist for your specific configuration before you begin installation.

The following information is required for all HP Service Guard cluster configurations.

Table 6-1 All HP Service Guard cluster configurations

Resource	Example
Virtual name for NetBackup:	vname
IP address:	10.209.14.54
Subnet for the virtual name:	10.209.14.0

The following information is required if you use HP Service Guard for different configurations.

Table 6-2 HP Service Guard with VxVM volume group

Resource	Example
Disk Group Name:	nbudg
Logical Volume Path:	dev/dsk/nbudg/nbuvol
Mount Point:	/opt/VRTSnbu
File System:	vxfs
Mount Options:	
Unmount Options:	
fsk Options:	

HP Service Guard with Veritas cluster volume manager Table 6-3

Resource	Example
Disk Group Name:	nbudg
Logical Volume Path:	/dev/dsk/nbudg/nbuvol
Mount Point:	/opt/VTRSnbu
File System:	vxfs
Mount Options:	
Unmount Options:	
fsk Options:	

HP Service Guard with LVM volume group Table 6-4

Resource	Example
Disk Group Name:	nbuvg
Logical Volume Path:	dev/nbuvg/lvo1
Mount Point:	opt/VRTSnbu
File System:	vxfs
Mount Options:	
Unmount Options:	
fsk Options:	

## Installing NetBackup on HP Service Guard cluster

This section describes how to install NetBackup Enterprise Server as a failover application in a Service Guard cluster. If you want to upgrade NetBackup, rather than complete an initial installation, you need to follow a different procedure.

See "Upgrading a NetBackup failover server on HP Service Guard Cluster" on page 68.

Review the following notes before you begin installation:

■ These instructions assume that this installation is a new installation of a NetBackup failover server.

- The NetBackup package name in a Service Guard cluster is always NetBackup. The user cannot configure this name.
- The following package ASCII file is installed with NetBackup. You can change the values for any of the timeout settings in this file. Do not make changes to any settings that are not related to timeouts.

/etc/cmcluster/netbackup/netbackup.config

**Note:** Cluster configuration is performed along with the installation process. Do not run the cluster config script to perform cluster configuration.

The following procedure describes how to install and configure a NetBackup failover server on a Service Guard cluster.

#### To install NetBackup on HP Service Guard cluster

- Fill out the checklist for all configurations and the checklist for your specific environment.
  - See "Preinstallation checklist for a NetBackup failover server installation on HP Service Guard cluster" on page 63.
- 2 Make sure that the shared disk is not mounted on any node in the cluster. If applicable, unmount the NetBackup shared mount point. Stop the volume the mount point is on and stop the disk group for that volume on all nodes of the cluster.
- Follow the instructions for how to install NetBackup in the *Symantec* NetBackup Installation Guide.

Be sure that you:

- Install NetBackup on each node to which it can failover.
- Use the virtual name for the NetBackup server name.

**Caution:** When you are prompted, you must provide the same virtual cluster name that you provided during the installation. This name is case-sensitive and must be in same format (FQDN/short) on all the nodes.

- When NetBackup is installed on the clustered setup a confirmation prompt is displayed.
  - When you install NetBackup on the first node, you are prompted to confirm creation of a NetBackup cluster. Type Y to set up NetBackup in HA mode.

- While you install NetBackup on the subsequent nodes, information of already created NetBackup cluster group is displayed. You are prompted to join the group.
- When you are prompted for cluster-specific configuration details, refer to the checklist and provide details accordingly.
- Allow NetBackup to be installed in a cluster. When a NetBackup failover server is installed:
  - On the first node, a single node cluster resource group for NetBackup is created and brought online.
  - On the other nodes, the installed node is added to the cluster resource group.
- Install any NetBackup database agents or options.
  - You must freeze the NetBackup group before you install any agents or options.
  - See "Installing or upgrading NetBackup database agents and options on HP Service Guard Cluster" on page 67.
- Continue with the configuration of NetBackup. See "Configuring NetBackup on HP Service Guard cluster" on page 66.

## Configuring NetBackup on HP Service Guard cluster

To configure NetBackup server in a cluster, do the following:

Table 6-5 Configuring NetBackup on HP Service Guard cluster

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.
	Catalog backup information is stored on the shared disk and does not need to be configured for each node.

Step	Action	
4	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.	
	See "About configuring backup policies for a NetBackup clustered server" on page 87.	
5	When you have completed configuration of NetBackup, verify that NetBackup can fail over properly in the cluster. See "Verifying NetBackup configuration" on page 89.	

Configuring NetBackup on HP Service Guard cluster (continued) Table 6-5

## Installing or upgrading NetBackup database agents and options on HP Service Guard Cluster

To install or upgrade database agents and options, NetBackup daemons must be brought offline without causing a failover. Service Guard must be configured to stop monitoring NetBackup, but keep NetBackup resources online (or frozen).

By default, robotic daemons and NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail. You can configure robot daemons and NetBackup options to failover NetBackup if a daemon or the option fails.

See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.

See "Configuring add-ons for monitoring (UNIX/Linux clusters)" on page 91.

#### To install or upgrade NetBackup database agents and options on HP Service Guard Cluster

Place NetBackup in a frozen state by executing the following:

```
cmmodpkg -d netbackup
```

2 Run the following command on the active node to disable the NetBackup agent monitor:

```
touch /usr/openv/netbackup/bin/cluster/frozen
```

- On the active node where NetBackup server is installed, install any database agents or options. See the appropriate NetBackup documentation for the agent or option for installation and configuration instructions.
- Perform the same installation on each inactive node.

After you complete the installations of the agents or options, run the following:

```
cmmodpkg -e netbackup
```

Run the following command on the active node to enable the NetBackup agent monitor:

```
rm -f /usr/openv/netbackup/bin/cluster/frozen
```

The NetBackup resources are brought online and Service Guard resumes monitoring the NetBackup resource.

#### Upgrading a NetBackup failover server on HP Service **Guard Cluster**

Follow these instructions to upgrade NetBackup failover server from NetBackup 6.0 and later.

**Note:** Before upgrading NetBackup on HP Service Guard cluster, please refer to technote 145810.

#### To upgrade a NetBackup failover server on HP Service Guard Cluster

Ensure that a good backup of your cluster environment exists that includes a catalog backup.

See "Configuring NetBackup catalog backups in a cluster" on page 86.

- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list must contain the name of each node on which NetBackup can run and the name of the virtual server.
- Place NetBackup in a frozen state by executing the following:

```
cmmodpkg -d netbackup
```

Run the following command on the active node to disable the NetBackup agent monitor:

```
touch /usr/openv/netbackup/bin/cluster/frozen
```

On active node, install the NetBackup server.

Note the following:

■ Follow the instructions for how to install NetBackup server as described in the Symantec NetBackup Installation Guide.

- If required to specify the server name, provide the virtual name of the server.
- 6 On each inactive node to which NetBackup may failover, install the NetBackup server.

Note the following:

- Follow the instructions for how to install NetBackup server as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.
- During an upgrade of a NetBackup in a Service Guard cluster you see the messages that indicate that the database is created twice. These messages appear because the database is created in the default location (/usr/openv/db/) during install bp. Later, it is moved or recreated on the shared disk.
- Run the following command:

```
cmmodpkg -e netbackup
```

Run the following command on the active node to enable the NetBackup agent monitor:

```
rm -f /usr/openv/netbackup/bin/cluster/frozen
```

The NetBackup resources are brought online and Service Guard resumes monitoring the NetBackup resource.

- 10 Bring the NetBackup resource group offline and online. See "Service Guard commands for bringing the resource group online or offline" on page 70.
- 11 On each node on which NetBackup server is installed, upgrade any NetBackup database agents or options. You must freeze the NetBackup group before you install any agents or options.

See "Installing or upgrading NetBackup database agents and options on HP Service Guard Cluster" on page 67.

12 Verify that NetBackup can failover properly in the cluster.

See "Verifying NetBackup configuration" on page 89.

## Service Guard commands for bringing the resource group online or offline

To bring the NetBackup resource group online or offline, special Service Guard commands must be used. See the Service Guard documentation for more information on these and other commands.

Table 6-6 describes the commands you use to bring the NetBackup resource group online or offline.

Table 6-6 **HP Service Guard commands** 

Task	Command
Bring the NetBackup resource group online	/usr/sbin/cmrunpkg netbackup
Bring the NetBackup resource group offline	/usr/sbin/cmhaltpkg netbackup
Verify that the NetBackup resource is online	/usr/sbin/cmviewcl

Chapter

# NetBackup on HACMP cluster for AIX

This chapter includes the following topics:

- About NetBackup on HACMP cluster for AIX
- Installation prerequisites for NetBackup on HACMP cluster for AIX
- Preinstallation checklist for a NetBackup failover server installation on HACMP cluster for AIX
- Installing NetBackup on HACMP cluster for AIX
- Configuring NetBackup on HACMP cluster for AIX
- Installing NetBackup database agents and options on HACMP cluster for AIX
- Upgrading a NetBackup failover server on HACMP cluster for AIX
- Bringing the NetBackup resource group online or offline

## About NetBackup on HACMP cluster for AIX

This topic provides information on how to install and configure NetBackup Enterprise Server as a highly available application with High Availability Cluster Multiprocessing (HACMP).

HACMP is a high-availability solution for cluster configurations. With HACMP you can monitor systems and application services, and restart services on a different system when hardware or software fails. Refer to the documentation for HACMP for a detailed understanding of how HACMP works and how it is installed and administered.

Refer to the Symantec NetBackup Administrator's Guide, Volume I, for a detailed understanding of how NetBackup is installed and administered.

NetBackup can be configured in a cluster as a non-failover server and as a standalone media server with virtual storage units. For more information, refer to the Symantec NetBackup in Highly Available Environments Administrator's

#### Installation prerequisites for NetBackup on HACMP cluster for AIX

This section contains information about the requirements that must be met before install and configure a NetBackup failover server in a HACMP environment.

- Verify that HACMP and NetBackup Enterprise Server 7.5 support your hardware. For a list of supported storage devices, visit the following Web site. Also consult the HACMP documentation. http://entsupport.symantec.com
- Verify that supported version of AIX is installed.
- Verify that supported version of HACMP is correctly installed and configured. It also must pass cluster verification and synchronization.
- Physically connect the robotic devices and tape devices to each node where you want to install NetBackup). Connect devices by SCSI or Fibre Channel. Use OS commands to verify that all the devices are connected properly. Refer to the Symantec NetBackup Device Configuration Guide.
- Make sure that each node in the cluster, where you want to install NetBackup, is RSH equivalent. As the root user you need to be able to perform a remote logon to each node in the cluster without entering a password. This ability is only necessary for installation, upgrades, and configuration of the NetBackup server and any NetBackup database agents and options. When installation and configuration are complete, RSH can be disabled.
- There must be a pre-existing file system available for use by the NetBackup resource group that is configured on all nodes. This file system must be resident on a volume group that is accessible to all nodes where you want to configure NetBackup. It must not be configured as a resource for an existing HACMP resource group. It must not be configured to mount at boot time on any node.
- Verify that you have a service IP address and an associated name (virtual name) to configure for NetBackup. This name and address must be present in the /etc/hosts file on all nodes before you install NetBackup.

- If you use IPAT by IP Replacement for your service address, then it must be configured in HACMP. The service address must be configured before you start installing NetBackup. The service address must not already be assigned to a resource group. This configuration must be done before you install NetBackup.
- If you use IPAT by IP aliasing, you do not need to configure the service address in HACMP before you install NetBackup. The service address must conform to the restrictions that are described in topic entitled "Planning Cluster Network Connectivity" of the HACMP Planning and Installation Guide. If you have already configured the service, it must not be assigned to a resource group already.
- Before you configure NetBackup, the cluster must be stable and able to complete a successful verification and synchronization.
- Verify that you have the NetBackup Enterprise Server 7.5 installation program and a valid license key.

## Preinstallation checklist for a NetBackup failover server installation on HACMP cluster for AIX

The NetBackup Enterprise Server requests certain cluster-related information during installation. Fill out the checklist for all configurations and the checklist for your specific configuration before you begin installation.

The following information is required for all HACMP cluster configurations.

All HACMP cluster configurations Table 7-1

Resource	Example
NetBackup Resource Group Name:	netbackup
NetBackup Server Resource Name:	nbu_server
Mount Point for the Shared Storage:	/nbha1
Top-level Directory on Shared Storage:	/nbha1/dir1

The following information is required if you use HACMP.

Table 7-2 HACMP with IPAT by IP aliasing

Resource	Example
NetBackup Virtual Name:	vname

Table 7-2 HACMP with IPAT by IP aliasing (continued)

Resource	Example
HACMP Network Name:	net_ether_01
Table 7-3 HACMP with IPAT by IP replacement	
Resource	Example
NetBackup Virtual Name:	vname

## Installing NetBackup on HACMP cluster for AIX

This topic describes how to install NetBackup Enterprise Server as a failover application on HACMP cluster.

The following procedure describes how to install a NetBackup failover server in an HACMP cluster.

Note: You can ignore the following type of warning message from the cluster configuration script. These messages are generated during the verification and synchronization whenever there are multiple addresses on a network interface.

Warning: There may be an insufficient number of communication interfaces that are defined on node: blazer, network: net ether 01. Multiple communication interfaces are recommended for networks intending to use IP aliasing.

#### To install NetBackup on HACMP cluster for AIX

- Fill out the checklist for all configurations and the checklist for your specific environment.
  - See "Preinstallation checklist for a NetBackup failover server installation on HACMP cluster for AIX" on page 73.
- The volume group of the pre-existing file system that NetBackup uses must be varied-on, on the node from which you want to start clustered installation of NetBackup. If the volume group is not varied-on, the installer may not detect it as a shareable file system. Use the following command to vary-on the volume group:

varyonvg <volume group name>

Follow the instructions for how to install NetBackup in the Symantec NetBackup Installation Guide.

Be sure that you:

- Install NetBackup on each node to which it can failover.
- Use the virtual name for the NetBackup server name.

Caution: When you are prompted, you must provide the same virtual cluster name that you provided during the installation. This name is case-sensitive and must be in same format (FQDN/short) on all the nodes..

- When NetBackup is installed on the clustered setup a confirmation prompt is displayed.
  - When you install NetBackup on the first node, you are prompted to confirm creation of a NetBackup cluster. Type Y to set up NetBackup in HA mode.
  - While you install NetBackup on the subsequent nodes, information of already created NetBackup cluster group is displayed. You are prompted to join the group.
- When you are prompted for cluster-specific configuration details, refer to the checklist and provide details accordingly.

Allow NetBackup to be installed in a cluster. When a NetBackup failover server is installed:

- On the first node, a single node cluster resource group for NetBackup is created and brought online.
- On the other nodes, the installed node is added to the cluster resource group.
- Install any NetBackup database agents or options.

You must stop the NetBackup group before you install any agents or options.

See "Installing NetBackup database agents and options on HACMP cluster for AIX" on page 76.

Continue with the configuration of NetBackup. See "Configuring NetBackup on HACMP cluster for AIX" on page 75.

## Configuring NetBackup on HACMP cluster for AIX

To configure NetBackup server in a cluster, do the following:

Step	Action
1	Review the guidelines for how to configure NetBackup.
	See "NetBackup configuration guidelines" on page 83.
2	Configure the devices in the cluster.
	See "Device configuration guidelines" on page 84.
	See "Configuring devices" on page 85.
	<b>Note:</b> Devices must be configured on each node in the cluster.
3	Verify that the entries for the NetBackup Catalog backups are correct.
	See "Configuring NetBackup catalog backups in a cluster" on page 86.
	Catalog backup information is stored on the shared disk and does not need to be configured for each node.
4	Configure backup policies. Backup policies are stored on the shared disk and do not need to be configured for each node.
	See "About configuring backup policies for a NetBackup clustered server" on page 87.
5	When you have completed configuration of NetBackup, verify that NetBackup can fail over properly in the cluster.
	See "Verifying NetBackup configuration" on page 89.

Table 7-4 Configuring NetBackup on HACMP cluster for AIX

## Installing NetBackup database agents and options on HACMP cluster for AIX

To install database agents and options, NetBackup daemons must be brought offline without causing a failover. HACMP must be configured to stop monitoring NetBackup, but keep NetBackup resources online.

By default, robotic daemons and NetBackup options (such as NetBackup Vault) do not cause NetBackup to failover if they fail. You can configure robot daemons and NetBackup options to failover NetBackup if a daemon or the option fails.

See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.

See "Configuring add-ons for monitoring (UNIX/Linux clusters)" on page 91.

#### To install NetBackup database agents and options on HACMP cluster for AIX

Enter the following command to disable application monitoring for the NetBackup resource group.

```
smitty hacmp
```

- 2 Choose System Management (C-SPOC).
- 3 Choose HACMP Resource Group and Application Management.
- 4 Choose Suspend/Resume Application Monitoring.
- 5 Choose Suspend Application Monitoring.
- 6 Select the NetBackup server and press **Enter**.
- Run the following command on the active node to disable the NetBackup agent monitor:

```
touch /usr/openv/netbackup/bin/cluster/frozen
```

- On the active node where NetBackup server is installed, install or upgrade any database agents or options. See the appropriate NetBackup documentation for the agent or option for installation and configuration instructions.
- On the inactive node, perform the same installation.
- 10 Run the following command on the active node to enable the NetBackup agent monitor:

```
rm -f /usr/openv/netbackup/bin/cluster/frozen
```

**11** Enter the following command to enable application monitoring for the NetBackup resource group.

```
smitty hacmp
```

- 12 Choose System Management (C-SPOC).
- 13 Choose HACMP Resource Group and Application Management.
- 14 Choose Suspend/Resume Application Monitoring.
- 15 Choose Resume Application Monitoring.
- **16** Select the NetBackup server and press **Enter**.

## Upgrading a NetBackup failover server on HACMP cluster for AIX

Follow these instructions if you want to upgrade from NetBackup 6.0 and later.

**Note:** NetBackup does not support conversion of an existing non-failover NetBackup server to a failover NetBackup server. Contact Symantec Enterprise technical support.

#### To upgrade a NetBackup failover server on HACMP cluster for AIX

- Ensure that a good backup of your cluster environment exists that includes a catalog backup.
  - See "Configuring NetBackup catalog backups in a cluster" on page 86.
- For each NetBackup server that runs outside of the cluster, ensure that the server list is accurate. This list should contain the name of each node where NetBackup can run and the name of the virtual server.
- Enter the following command to disable application monitoring for the NetBackup resource group.

```
smitty hacmp
```

- Choose System Management (C-SPOC).
- 5 Choose HACMP Resource Group and Application Management.
- 6 Choose Suspend/Resume Application Monitoring.
- 7 Choose Suspend Application Monitoring.
- 8 Select the NetBackup server and press Enter.
- On the active node, install the NetBackup server software.

#### Note the following:

- Follow the instructions for how to install NetBackup server as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.
- 10 On each inactive node to which NetBackup may failover, install the NetBackup server software.

Note the following:

- Follow the instructions for how to install NetBackup server as described in the Symantec NetBackup Installation Guide.
- If required to specify the server name, provide the virtual name of the server.
- 11 On each inactive node where NetBackup server is installed, install or upgrade any database agents or options. See the appropriate NetBackup documentation for the agent or option for installation and configuration instructions.
- **12** On the active node, perform the same installation.
- 13 Run the following command on the active node to enable the NetBackup agent monitor:

```
rm -f /usr/openv/netbackup/bin/cluster/frozen
```

**14** Enter the following command to enable application monitoring for the NetBackup resource group.

```
smitty hacmp
```

- 15 Choose System Management (C-SPOC).
- 16 Choose HACMP Resource Group and Application Management.
- 17 Choose Suspend/Resume Application Monitoring.
- 18 Choose Resume Application Monitoring.
- **19** Select the NetBackup server and press **Enter**.
  - The NetBackup resources are brought online and Service Guard resumes monitoring the NetBackup resource.
- **20** Bring the NetBackup resource group offline and online.
- 21 On each node where NetBackup server is installed, upgrade any NetBackup database agents or options.
  - You must freeze the NetBackup group before you install any agents or options.
  - See "Installing NetBackup database agents and options on HACMP cluster for AIX" on page 76.
- **22** Verify that NetBackup can failover properly in the cluster.
  - See "Verifying NetBackup configuration" on page 89.

## Bringing the NetBackup resource group online or offline

The SMIT tool manages any resource group operations. Use this tool to bring the NetBackup resource group online or offline and to move the location of the resource group.

#### To bring the NetBackup resource group online

Enter the following command.

smitty

- 2 Choose Communications Applications and Services.
- 3 Choose HACMP for AIX.
- 4 Choose System Management (C-SPOC).
- 5 Choose HACMP Resource Group and Application Management.
- 6 Choose Online Group.
- Choose the group that you want to bring online.

#### To bring the NetBackup resource group offline

Enter the following command.

smitty

- 2 Choose Communications Applications and Services.
- 3 Choose HACMP for AIX.
- 4 Choose System Management (C-SPOC).
- 5 Choose HACMP Resource Group and Application Management.
- 6 Choose Offline Group.
- 7 Choose the group that you want to bring offline.

Chapter 8

# Configuring NetBackup

#### This chapter includes the following topics:

- NetBackup configuration overview
- NetBackup configuration guidelines
- Device configuration guidelines
- Configuring devices
- Configuring NetBackup catalog backups in a cluster
- About configuring backup policies for a NetBackup clustered server
- What to back up
- Guidelines for backing up local disks in a cluster
- Guidelines for backing up the shared disks
- Verifying NetBackup configuration
- Configuring robotic daemons for monitoring (UNIX/Linux clusters)
- Configuring additional services (UNIX/Linux clusters)
- Configuring add-ons for monitoring (UNIX/Linux clusters)
- Configuring additional services (Windows)
- Configuring add-ons for monitoring (Windows)
- About adding license keys

## NetBackup configuration overview

Configuration of NetBackup includes the creation of storage devices, volumes, the catalog backup, and backup policies. This configuration can be completed most easily with the NetBackup Configuration Wizards in the NetBackup Administration Console. Refer to the Symantec NetBackup Administrator's Guide, *Volume I*, for more details for instructions on how to perform these steps manually. (See information for configuring NetBackup without wizards.) Refer to Table 8-1 before you configure NetBackup.

Table 8-1 summarizes the information that applies to each cluster environment.

Table 8-1 Configuring NetBackup

Cluster Type	Section	Description
All	See "NetBackup configuration guidelines" on page 83.	General guidelines to follow when you configure the NetBackup server in a cluster.
All	See "Device configuration guidelines" on page 84.	General guidelines to follow when you configure devices for a NetBackup server in a cluster.
All	See "Configuring devices" on page 85.	Device configuration guidelines.
All	See "Configuring NetBackup catalog backups in a cluster" on page 86.	Instructions for verifying NetBackup Catalog Backup entries are correct.
All	See "About configuring backup policies for a NetBackup clustered server" on page 87.	Configuring automatic backup policies.
All	See "Verifying NetBackup configuration" on page 89.	Instructions to verify that NetBackup is configured correctly.
UNIX/Linux	See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.	How to configure robotic daemons to fail over NetBackup
UNIX/Linux	See "Configuring add-ons for monitoring (UNIX/Linux clusters)" on page 91.	How to configure NetBackup add-on products to fail over NetBackup in a UNIX/Linux cluster.

Cluster Type	Section	Description
Windows	See "Configuring add-ons for monitoring (Windows)" on page 92.	How to configure NetBackup add-on products to fail over NetBackup in Windows.
All	See "About adding license keys" on page 92.	Additional license keys in a cluster environment.

Configuring NetBackup (continued) Table 8-1

## NetBackup configuration guidelines

Review the following guidelines before you configure NetBackup.

- To ensure that all nodes in the NetBackup failover group are properly registered in the EMM database, you must failover the NetBackup Group to all nodes in the NetBackup cluster group.
- The NetBackup server list must be set up correctly on each node where NetBackup is configured as a failover server. For NetBackup in a clustered environment, the virtual server name must appear first. After that name, include the node names within the NetBackup group.
- For each NetBackup server that runs outside of the cluster, the server list must contain the name of each node where NetBackup can run. The list must also contain the name of the virtual server.
- NetBackup depends on names to route information between participants in the backup and restore process. Therefore, the use of names must be consistent within a NetBackup configuration. Specific node names and virtual names should not be used interchangeably.
- CLIENT NAME should be set to the name of the node.
- CLUSTER NAME should be the virtual server name that is dedicated to the NetBackup Application that runs on the cluster.
- When you make changes to the NetBackup configuration on the active node, be sure to apply the same changes to each node in the cluster.
- NetBackup Server Host Properties in a cluster
  - The NetBackup Administration Console obtains node information from the EMM database. Therefore, changes to the Host Properties only affect the nodes that are already registered in the EMM database. (You change the Host Properties only when you fail over to the NetBackup Group to each node.)

- All host names that are listed in the **Properties** panel can have their host properties updated with the Host Properties user interface. The exception is the Authorization host property, which is only updated on the active node.
- The "Add to All" hosts functionality is applicable only for a clustered master server and not for clustered media servers. To update Host Properties on clustered media servers, the user needs to update each node individually or select multiple nodes of the clustered media server.
- Configuration information is stored on the shared disk and cannot be configured separately for each node. (This information includes backup policies, storage units, and the NetBackup catalog backup.) All other configuration changes must be applied by moving the NetBackup server to each node.
- By default, NetBackup tries to complete a backup job two times (within a 12-hour window) before it allows the job to fail. Backup attempts may be exhausted before the failover of the NetBackup media server completes. If this situation happens, increase the **Scheduled backup attempts** setting to 6. You can also avoid this problem; set the **Job retry delay** setting to a lower value.
- The **Job retry delay** setting should be set lower to increase the likelihood that NetBackup is able to initiate all scheduled backups.
- The server list for each client you want to back up should contain the name of each node where NetBackup can run. This list should also contain the name of the virtual server.

## **Device configuration guidelines**

The following are guidelines for configuring the devices for a clustered NetBackup server:

- Choose the **SCSI Persistent reserve** protection option, if possible. The use of persistent reserve is recommended, but take care to ensure that your hardware supports it correctly. See the Symantec NetBackup Administrator's Guide, Volume II for more information.
  - With this option, NetBackup can recover and use a reserved drive after a failover (if NetBackup owns the reservation). If you use SPC-2 SCSI reserve, a drive reset usually is required because the reservation owner is inoperative. Consult the Symantec NetBackup Administrator's Guide for more information on how to reset a drive and on the **Enable SCSI Reserve** setting.
- Devices that are attached to one node but not to the other node are available only when the node where they are attached is online. For a NetBackup failover master server, attach all of the devices to each node where NetBackup is

installed. Use shared SCSI or Fibre Channel connections as necessary to share the devices.

- For a NetBackup media server failover configuration, configure devices from the NetBackup master server with the active node name as the NetBackup media server name.
- For any tape devices that are in a robotic library, ensure that the robot drive number field is set correctly. Use the drive numbering scheme that the manufacturer of the robotic library has implemented. NetBackup considers the first drive in the robot as robot drive number 1. If the manufacturer's drive numbering scheme starts with a different number such as 0, adjust it accordingly.
- Ensure that the robot numbers the failover server uses are consistent on all servers that use that robot. If the robot number that is defined on one node. does not match the number that is defined on another node, backups may fail.
- When you create the storage units that reside on the cluster, select the virtual name of the failover NetBackup server for the **Media server** setting.
- If you choose **Any server** for the media server when you create a storage unit, NetBackup selects the virtual NetBackup server when it performs any backup and restore operations.

## Configuring devices

This section describes how to configure devices in NetBackup.

**Note:** To accommodate disparate SCSI connections on each node of the cluster, you must configure devices on each node. First, configure the devices on the active node. Move the NetBackup group to another node and configure the devices on that node. Then move NetBackup to another node and configure the devices on that node, etc.

You can configure NetBackup to failover if a robotic device fails.

See "Configuring robotic daemons for monitoring (UNIX/Linux clusters)" on page 89.

#### To configure devices

- Review the device configuration guidelines.
  - See "Device configuration guidelines" on page 84.
- On the active node, run the Device Configuration Wizard. This wizard automatically discovers and configures the devices and it creates storage units for those devices.
  - Symantec recommends that you use the Device Configuration Wizard to configure devices.
- Move the NetBackup group to another node.
- 4 Refresh the view in the Media and Device Management utility.
- 5 Run the Device Configuration Wizard.
- Continue to configure the devices on each node in the cluster. Repeat step 3 through step 5.

If device paths are not displayed after you refresh the Devices node or run tpconfig, the active node of the cluster is not configured properly.

#### To add new devices

Follow the same procedure as when you initially configured devices in the cluster. First, configure the devices on the active node. Move the NetBackup group to another node and configure the devices on that node. Then move NetBackup to another node and configure the devices on that node, and so on.

## Configuring NetBackup catalog backups in a cluster

For complete information on how to configure and run online catalog backups, refer to the Symantec NetBackup Administrator's Guide. For information on recovery of the NetBackup catalog, see the Symantec NetBackup Troubleshooting Guide.

**Note:** An online catalog backup does not back up information on the inactive nodes. You must create a separate policy as described in the following step.

#### To configure an online, hot catalog backup in a cluster

- Follow the instructions for creating online catalog backups as described in the Symantec NetBackup Administrator's Guide.
- Create a policy to back up the following directory on each node in the cluster.

Windows install path\netbackup\var

UNIX/Linux /usr/openv/var

## About configuring backup policies for a NetBackup clustered server

To back up all data in a cluster, create backup policies that back up the local disks, shared disks, and database files in the cluster.

Review the following topics:

See "What to back up" on page 87.

See "Guidelines for backing up local disks in a cluster" on page 88.

See "Guidelines for backing up the shared disks" on page 88.

## What to back up

Back up the following to protect all data in the cluster, including file systems and databases:

- Local disks on each node. See "Guidelines for backing up local disks in a cluster" on page 88.
- All disks that attach to the shared SCSI bus. See "Guidelines for backing up the shared disks" on page 88.
- Virtual servers, which may contain data or contain database applications. Use NetBackup database agents to back up databases.
- In MSCS and VCS for Windows clusters, also be sure to back up the System State and Shadow Copy Components on each node. For MSCS clusters, you must also back up the cluster quorum. The cluster quorum contains recovery information for the cluster and information about changes to the cluster configuration. The cluster quorum is included in the System State or Shadow Copy Components backup.

See "Guidelines for backing up local disks in a cluster" on page 88.

## Guidelines for backing up local disks in a cluster

To protect the data on the node's local disks, configure a policy that includes the cluster node names in the client list. In addition to this policy, you must also configure a separate policy to back up the shared disks.

See "Guidelines for backing up the shared disks" on page 88.

The following are guidelines for configuring the policy to back up local disks:

- If you have a failover media server, when you create a backup policy, select the storage unit that you created for the failover media server.
- If NetBackup is installed on the cluster as separate NetBackup media servers, configure a policy for each node. Each policy should include the cluster node name as a client. For each policy, select the storage unit that you created for the NetBackup media server that is installed on that cluster node.
- In the **Backup Selections** list, add all the local disks (excluding the shared disks).
- For Windows cluster, always include System\_State:\ or Shadow Copy Components:\ in the file list to back up the System State for each cluster node. In a policy for an MSCS cluster, System\_State:\ or Shadow Copy Components:\ also backs up the cluster quorum information.

## Guidelines for backing up the shared disks

To protect the data on the shared disks, configure a policy that includes the virtual server name in the **Clients** list. This server name must be associated with the shared disk. In addition to this policy, you must also configure a separate policy to back up the local disks.

See "Guidelines for backing up local disks in a cluster" on page 88.

The following are guidelines for configuring the policy to back up the shared disks:

- If you have a failover media server, when you create a backup policy, select the storage unit that you created for the failover media server.
- If NetBackup is installed on the cluster as separate NetBackup media servers, select a storage unit that was created for one of the media servers. Or, select Any Available.
- If a storage unit does not have local, direct access to the shared disk drives, the data is backed up across the network. This action occurs even if the storage unit refers to a media server running on a node of the cluster that does not currently have control of the shared disk drives. In the **Backup Selections** list, specify the drive letters or mounted directories of the shared disks.

Note that a backup fails if two separate cluster nodes control the cluster resource that defines the virtual server name and the resource that defines the shared disks. Ensure that the virtual server name and the shared disks are configured to failover together so that the same node always controls them.

System State information is included in the backup of the node's local disks. You do not need to include System State:\ or Shadow Copy Components:\ in the file list for this policy.

## Verifying NetBackup configuration

After you complete the configuration of storage devices, volumes, the catalog backup, and the backup policies, verify that NetBackup fails over properly in the cluster.

#### To verify NetBackup configuration

- Confirm that the NetBackup is online on the primary node, then determine if the following can be completed successfully:
  - Scheduled backups
  - User-directed backups
  - NetBackup catalog backups
  - Server-and user-directed restores
- Switch the NetBackup resource group to another node and perform the same tests in the previous step. Repeat for each node in the cluster where NetBackup is installed.

## Configuring robotic daemons for monitoring (UNIX/Linux clusters)

By default, robotic daemons do not cause NetBackup to failover if they fail. You can configure robot daemons to failover NetBackup if a daemon fails.

**Note:** You must configure robots before you perform the following instructions. Refer to the Symantec NetBackup Installation Guide for instructions on how to configure storage devices.

#### To configure NetBackup to failover if a robotic daemon fails

- 1 Configure your robots on each node in the cluster.
- 2 Run the following script:

```
/usr/openv/netbackup/bin/cluster/cluster config -r
```

- 3 Choose a (Add).
- Select your robot from the list.

Multiple robots can be selected.

#### To remove a robotic daemon from monitoring

Run the following script:

```
/usr/openv/netbackup/bin/cluster/cluster config -r
```

- Choose d (Delete).
- 3 Select the robot type you want to remove.

## Configuring additional services (UNIX/Linux clusters)

By default, all the necessary NetBackup services are added to the NetBackup Cluster Group.

#### To add a service to the NetBackup Cluster Group

Run the following command:

```
/usr/openv/netbackup/bin/bpclusterutil
-addSvc "ServiceName"
```

This command brings up the service when the group comes online, but the service is not monitored. If the service Service Name fails, it does not cause the group to failover.

#### To delete a service from the NetBackup Cluster Group

Run the following command:

```
/usr/openv/netbackup/bin/bpclusterutil
-deleteSvc "ServiceName"
```

If you delete a critical service, cluster do not failover if that service fails.

## Configuring add-ons for monitoring (UNIX/Linux clusters)

By default, add-on products (such as NetBackup Vault) do not cause NetBackup to failover if they fail. These products can be configured to failover NetBackup if an add-on product fails.

#### To enable monitoring for the optional services

Run the following command:

```
/usr/openv/netbackup/bin/bpclusterutil
-enableSvc"ServiceName"
```

#### To disable monitoring for the optional services

Run the following command:

```
/usr/openv/netbackup/bin/bpclusterutil
-disbleSvc"ServiceName"
```

Monitoring can be turned on or off for only NetBackup Vault Service and NetBackup Key Management Service. The ServiceName parameters for these services are nbvaultand nbkms.

## Configuring additional services (Windows)

By default, all the necessary NetBackup services are added to the NetBackup Cluster Group.

#### To add a service

Run the following command:

```
<NetBackup install path>\NetBackup\bin\bpclusterutil.exe
-addSvc "ServiceName"
```

This command brings up the service when the group comes online, but the service is not monitored. If the service ServiceName fails, it does not cause the group to failover.

#### To delete a service from a NetBackup Cluster Group

Run the following command:

```
<NetBackup install path>\NetBackup\bin\bpclusterutil.exe
-deleteSvc "ServiceName"
```

## Configuring add-ons for monitoring (Windows)

By default, add-on products (such as NetBackup Vault) do not cause NetBackup to failover if they fail. These products can be configured to failover NetBackup if an add-on product fails.

#### To enable monitoring for the optional services

Run the following command:

```
<NetBackup install path>\NetBackup\bin\bpclusterutil.exe
-enableSvc "ServiceName"
```

#### To disable monitoring for the optional services

Run the following command:

```
<NetBackup install path>\NetBackup\bin\bpclusterutil.exe
-disbleSvc "ServiceName"
```

Monitoring can be turned on or off only for NetBackup Vault Service and NetBackup Key Management Service. The ServiceName parameters for these services are "NetBackup Vault Service", "NetBackup Key Management Service"

## About adding license keys

If you add other licenses at the end of a Windows master server installation, then you must failover and add these licenses to each node in the cluster. If you add new licenses later, you also need to failover to add these licenses to each node in the cluster. On Windows, you can also use the bpminlicense command. On UNIX/Linux servers, you can alternatively use the get license command to add license keys without having to failover to each node.

Some features and products (such as NetBackup Shared Storage Option) require the keys to also be installed on the media server. If you have a NetBackup failover media server, any of these licenses must also be added to each node in the cluster.

Chapter 9

## Operational notes

This chapter includes the following topics:

- General notes on clustered master server administration
- About delay in detecting of loss of connection (MSCS and VCS on Windows)
- About MSCS clusters
- About NetBackup cluster application management
- Logging information
- About NetBackup's IPv6 support

# General notes on clustered master server administration

Consider the following operational issues to consider when you use NetBackup as a failover server:

- If a NetBackup server fails over and backup jobs are running, one of the following things happen:
  - If checkpoint restart is enabled for backup jobs for the policy, any backups that were running are resumed at the last checkpoint. Note that the schedule window must permit the job to be resumed.
  - If checkpoint restart is not enabled for backup jobs, any backup jobs that were running fail. These jobs show up as failed jobs in the Activity Monitor or NetBackup reports. Scheduled backup jobs are retried according to the normal retry logic. (See the **Job retry delay** and the **Schedule backup attempts** attributes). The schedule window and so on must permit the retry of the job. After a failover occurs, the user must restart user-directed backups and manual backups.

Refer to the Symantec NetBackup Administrator's Guide, Volume I, for more information on checkpoint restart, Job retry delay, and Scheduled backup attempts.

- After a failover occurs on a NetBackup failover server, it takes time for the tape devices and media servers to be reset. For example, a tape may have to be rewound before it is made available. Until the device is again ready for use, you may see errors. For example, you may see error 213 (no storage units available for use) or error 219 (the required storage unit is unavailable).
- After a failover, NetBackup may change the status of a drive that is required for a backup or restore to PEND. More information is available about how to use the NetBackup Administration Console Device Monitor to resolve a pending request or action.
  - See the Symantec NetBackup Administrator's Guide, Volume I.
- If you have the NetBackup Administration Console open when a failover occurs, you need to refresh the display. This refresh ensures that the services on the active node are displayed correctly. In the NetBackup Administration Console (from the View menu) click **Refresh All**.
- The backup and restore process is the same whether you are in a cluster or a non-cluster environment. See the Symantec NetBackup Troubleshooting Guide for further information on backup and archive processes and on restore processes.
- TIR is not supported for clustered shared drives.

## About delay in detecting of loss of connection (MSCS and VCS on Windows)

There may be a delay in the detection of the loss of a connection from a NetBackup Windows master server to a media server. For example, consider that a media server goes down while running a backup. There may be a delay on the master server before it detects that the media server is no longer available. It may first appear that a problem exists with the NetBackup Windows master server. This delay is a result of a certain TCP/IP configuration parameter on Windows called KeepAliveTime. By default, this parameter is set to 7,200,000 (two hours, in milliseconds). More information about the KeepAliveTime and other associated TCP/IP configuration parameters on Windows may be found in the following Microsoft knowledge base articles: Q140325 and Q120642.

Because of the delay jobs appear to be active on that media server even after the connection to the media server has gone down. In some cases an undesirable delay can occur before the current backup job fails. NetBackup tries to retry the job on a different media server, if one is available.

This delay is especially noticeable when the media server in question is a NetBackup failover media server that runs in a Microsoft Cluster Server (MSCS) environment. NetBackup relies upon the NetBackup master server to restart the NetBackup jobs that were running on the NetBackup failover media server when a failover occurs.

You may want to modify the **KeepAliveTime** configuration parameter on the NetBackup Windows master server. However, exercise extreme caution. The parameter is a system-wide parameter that affects all TCP/IP communications for that system. Also, it may be advantageous to modify this parameter on Windows media servers that use the failover master server.

### About MSCS clusters

Note the following points before you use NetBackup as a failover server in an MSCS environment:

- If there are no tape devices configured on the controlling node of the NetBackup failover server, the NetBackup Device Manager service resource takes itself offline. If you do not intend to configure tape devices for the NetBackup failover server, you may want to delete the NetBackup Device Manager service resource from the NetBackup group. This way you can avoid seeing the group in a warning state or failed state.
- For MSCS clusters with three or more nodes, the MSCS Move Group command lists all of the nodes in the cluster. You must pick a node that is valid for the NetBackup failover server to use. (MSCS displays all nodes in the cluster, even those nodes where NetBackup has not been installed.)
- Also refer to the information in the previous sections for further notes that are relevant to all cluster environments.

## About NetBackup cluster application management

Only use the cluster application's management tools to start and to stop NetBackup in the cluster. In a UNIX or Linux environment, do not use bp. start all or bp.kill all to start or stop NetBackup.

## Logging information

NetBackup records information on the processes. You can use this information to determine why a server has failed over. Logging information is highly useful for troubleshooting.

UNIX and Linux logging

Logging information for UNIX and Linux platforms can be found at the following locations:

- Cluster configuration-related information is recorded in log.cc. <date> file, which is located at /usr/openv/netbackup/logs/cluster. The configuration scripts creates the log directory, if it is not present.
- Cluster upgrade-related information is recorded in trace.cluster upgrade.process ID>file, which is located at
  - /usr/openv/netbackup/logs/cluster.
- Agent (Online/Offline/Monitor) related information is recorded inlog. <date> file, which is located at /usr/openv/netbackup/logs/cluster
- Add the following configuration parameter "DEBUG LEVEL=1" to the /usr/openv/netbackup/bin/cluster/NBU RSP file to generated detailed logging.

**Note:** This configuration is node-specific and affects the logging level on that enabled node. Enable this option only when required and turn it off when not required for storage considerations.

#### Windows logging

The cluster configuration status box reports details about cluster configuration. If problems occur, see the status box. Details of the cluster configuration steps that occur during the install are recorded in the install logs. In the logs, you have a record of the parameters used to perform cluster configuration commands and their return statuses.

Logging information for Windows platform can be found at the following locations:

- Cluster configuration and upgrade related information is recorded in ClusterConfig. <timestamp>.log file, which is located at %ALLUSERSPROFILE%\Symantec\NetBackup\InstallLogs.
- For Agent (MSCS) use Event Viewer.
- For Agent (VCS) use NetBackupVCS agent log file, which is located in the log directory of VCS.

## About NetBackup's IPv6 support

To use IPv6 with NetBackup:

- Ensure that the underlying environment supports IPv6.
- The virtual name that is used for NetBackup must always resolve to single IP address. The virtual name can resolve to either single IPv4 or single IPv6 address. If the virtual name resolves to multiple IP addresses, NetBackup does not function properly.
- Migration from IPv4 to IPv6 and vice versa is not supported. Thus, all the upgrades are of IPv4 type.

**Note:** The NetBackup installer uses the IPv4 type to create IPv6 resource which causes problems in the NetBackup cluster service group going online successfully. Refer Technote 174144 for the workaround.

For more information about using IPv6 with NetBackup, refer to the *Symantec* NetBackup Administrator's Guide.

For supported versions of cluster technologies, see the *NetBackup Cluster* Compatability Matrix.

Appendix A

# NetBackup master server in a cluster using multiple interfaces

This appendix includes the following topics:

- About NetBackup master server in a cluster using multiple interfaces
- Requirements for use of a NetBackup master server in a cluster with multiple interfaces
- Configuring the NetBackup master server in a cluster using multiple interfaces

# About NetBackup master server in a cluster using multiple interfaces

In a cluster environment, all NetBackup master server traffic and communication flow through the network interface that is associated with the virtual name of the master server. With the ANY\_CLUSTER\_INTERFACE configuration parameter, you can allow communication through any of the interfaces available to the NetBackup master server.

The following figure depicts a scenario where a clustered NetBackup master server has access to two separate networks (168.1 and 192.1). Client computers are attached to both networks and must be backed up. The virtual name for the master server (for example, NBUV168) can only be associated with one of the networks. So all NetBackup communication only occurs over that specific interface. Clients on other interfaces cannot be contacted.

Figure A-1 shows NetBackup in an environment with multiple network interfaces.

Client 1 Client 2 168.01 network NBUV168 Media168 NB168 NA168 Private Network Media serve Node 2 Node 1 Media192 NB192 NBUV192 NetBackup clustered master server 192.1 network Client 3 Client 4

Figure A-1 NetBackup in an environment with multiple network interfaces

## Requirements for use of a NetBackup master server in a cluster with multiple interfaces

The following requirements exist when you use a NetBackup master server in a cluster with multiple interfaces:

- A cluster environment that is properly installed and configured.
- Verify that you have a clustered NetBackup master server that is functional.
- Enterprise Media Manager (EMM) must reside on the master server.
- A unique virtual name (IP address and host name) associated with each interface.
- NetBackup 6.0 MP1 or higher.

## Configuring the NetBackup master server in a cluster using multiple interfaces

Perform the following steps to allow communication over an additional network interface.

#### To configure the NetBackup master server in a cluster using multiple interfaces

- For each additional interface, add a virtual name and IP address resource in the NetBackup cluster group.
  - This virtual name is the master server name the clients is referenced on their particular network.
- **2** Configure the ANY CLUSTER INTERFACE parameter.
- On Windows, perform the following steps.
  - In regedit, go to the following.

```
HKEY LOCAL MACHINE\SOFTWARE\VERITAS\NetBackup\CurrentVersion
\Confia
```

- Create a new DWORD value that is called ANY CLUSTER INTERFACE.
- Change the **Value Data** to 1.
- 4 On UNIX/Linux, add the following entry to the bp.conf.

```
ANY CLUSTER INTERFACE = 1
```

Add the following to the server list of the master server.

- The node names of the master server, for each network interface.
- The virtual name of the master server, for each network interface.

For example, to configure the master server in an environment with multiple network interfaces, add the following: NBUV168, NBUV192, NA168, NA192, NB168, NB192,

See Figure A-1 on page 100.

Add the node name of each media server to the media server list on the master server.

For example, add Media168 and Media192.

- Repeat step 2 through step 6 for all nodes where the NetBackup master server is installed.
- 8 Update the server list for all NetBackup clients.

The list must include all the possible names for the master server on their network. For example, for clients on the 168.1 network, include the server names NBUV168, NA 168, and NB 168. For clients on the 192.1 network, include the server names NBUV192, NA\_192, and NB\_192.

# Index

A	D
active/active application	device configuration
NetBackup as a 15	adding new devices 86
	attaching devices to all nodes 85
В	guidelines 84-85
backup policies 87	instructions for HP MC/Service Guard 86
backups	instructions for MSCS 86
and failovers 93	instructions for Sun Cluster 86
of local disks in a cluster 88	instructions for VCS 86
of shared disks 88	specifying active node name 85
what to back up in a cluster 87	
	E
C	Enable SCSI reserve 84
catalog backups	
hot backups 87	F
Checkpoint Restart 93	failover
CLIENT_NAME 83	and manually refreshing NetBackup
cluster configurations	Administration Console 94
mixed server types not supported 12	and storage unit errors 94
NetBackup failover server 12	definition 12
cluster quorum	when backup jobs running 93
restoring 22, 25	failover master servers 12
cluster solutions	failover media servers 12
supported 13	
CLUSTER_NAME 83	Н
cmhaltpkg 70	HACMP
cmmodpkg 67-68	backups in a 87
cmrunpkg 70	hardware requirements 72
cmviewel 70	installation and configuration 74
compatibility lists 14	installation prerequisites 72
configuration	monitoring NetBackup options 76, 91
of NetBackup 83–84 information stored on shared disk 84	monitoring robotic daemons 76, 90
server list 83	NetBackup database agents
usage of cluster aliases 83	installing or upgrading 76
usage of rode names 83	NetBackup options
verifying 89	installing or upgrading 76
vernying of	rsh equivalency 72
	upgrading a NetBackup failover server 78-79
	HP MC/Service Guard
	backups in a 87

HP MC/Service Guard (continued) device configuration 86 hardware requirements 62 installation and configuration 64 installation prerequisites 62 monitoring NetBackup options 67 monitoring robotic daemons 67 NetBackup database agents installing or upgrading 67 NetBackup options installing or upgrading 67 NetBackup resource group bringing offline 70 bringing online 70 verifying it is online 70 remshequivalency 63 shared disk configuration 62 HP MC/ServiceGuard monitoring NetBackup options 91 monitoring robotic daemons 90	Microsoft Cluster Server (MSCS) (continued) monitoring NetBackup options 92 Move Group 95 NetBackup cluster group name 19 NetBackup Device Manager 95 Possible Owners list 18 restoring the cluster quorum 22 upgrading a failover server 21 virtual name for NetBackup 18  N NetBackup Administration Console refreshing after failover 94 NetBackup Device Manager 95 NetBackup failover server installing in a MSCS 19–20, 44 installing in a VCS 44 NetBackup options monitoring on a MSCS cluster 92 monitoring on UNIX/Linux clusters 91
	NetBackup Server
<b>J</b>	supported in a cluster 15
Job retry delay 84, 93	non-failover servers converting to failover servers 14
K	n.
KeepAliveTime 95	P
L	pending requests 94 platforms supported for NetBackup in a cluster 14
license keys	_
adding to master server 92	R
adding to media server 92	robotic daemons
limitations 14	monitoring on UNIX/Linux clusters 89
LiveUpdate 14	robotic libraries 85
local disks	_
backups of 88	S
loss of connection, to NetBackup Windows server 94	Schedule backup attempts 93
	Scheduled backup attempts 84
M	SCSI persistent reserve 84
Microsoft Cluster Administrator	scstat 59
installing on all NetBackup servers 19	scswitch 56–59
Microsoft Cluster Server (MSCS)	server list 83
backups in a 87	for clients 84
device configuration 86	server types
disaster recovery 27	mixing 14 shared disks
hardware requirements 18 installation notes 19	and storage units 88
installation notes 19 installation prerequisites 18	storage units
loss of connection to NetBackup server 94	active node name as NetBackup media server 85
1000 of conficction to Netbackup server 94	active flour flame as iverbackup filedia selvel ob

storage units <i>(continued)</i> and NetBackup failover media servers 88	Veritas Cluster Server (VCS) for UNIX/Linux (continued)
and NetBackup non-failover media servers 88	upgrading a failover server 37
Sun Cluster	virtual name for NetBackup 30
backups in a 87	Veritas Cluster Server (VCS) for Windows
device configuration 86	installation notes 44
hardware requirements 52	11100411401011110000 11
	installing a NetBackup failover server 44
installation and configuration 53 installation notes 53	NetBackup cluster group name 44
	virtual name for NetBackup 43
installation prerequisites 52	Veritas Cluster Server (VCS) for Windows 2000/2003
monitoring NetBackup options 56, 91	backups in a 87
monitoring robotic daemons 56, 90	Clean 42
NetBackup database agents	detailed monitoring 47, 49
installing or upgrading 56	device configuration 86
NetBackup options	loss of connection
installing or upgrading 56	to NetBackup Windows server 94
NetBackup resource group	Monitor 42
bringing offline 59	NetBackup service group 44
bringing online 58	Offline 42
verifying it is online 59	Online 42
RSH equivalency 52	requirements 42
shared disk configuration 53	upgrading a failover server 46
upgrading a NetBackup failover server 57–58	virtual server name 12
supported cluster solutions 13	and backups 89
oupported tractor cordinate to	in the Clients list 88
т	m and enterto not do

#### .

tpconfig 86

#### V

Veritas Cluster Server (VCS) for UNIX/Linux backups in a 87 hardware requirements 30 installation notes 34 installing and configuring a NetBackup failover server 34 monitoring NetBackup options 37, 91 monitoring robotic daemons 90 NetBackup database agents installing 36-37 NetBackup options installing 36-37 monitoring 37 pre-installation checklist 31 robotic daemons monitoring 37 rsh equivalency 30 shared disk configuration 30 supported NetBackup agent for 37